

Telnet Environment Option

Status of this Memo

This document is an Internet Draft. Internet Drafts are working documents of the Internet Engineering Task Force (IETF), its Areas, and its Working Groups. Note that other groups may also distribute working documents as Internet Drafts.

Internet Drafts are draft documents valid for a maximum of six months. Internet Drafts may be updated, replaced, or obsoleted by other documents at any time. It is not appropriate to use Internet Drafts as reference material or to cite them other than as a "working draft" or "work in progress."

Please check the `ltd-abstracts.txt` listing contained in the internet-drafts Shadow Directories on `nic.ddn.mil`, `nnsf.net`, `nic.nordu.net`, `ftp.nisc.sri.com`, or `munari.oz.au` to learn the current status of any Internet Draft.

Abstract

This document specifies a mechanism for passing environment information between a telnet client and server. Use of this mechanism enables a telnet user to propagate configuration information to a remote host when connecting. Distribution of this memo is unlimited.

1. Command Names and Codes

ENVIRON	36
IS	0
SEND	1
INFO	2
VAR	0
VALUE	1
ESC	2
USERVAR	3

2. Command Meanings

IAC WILL ENVIRON

The sender of this command is willing to send environment variables.

IAC WONT ENVIRON

The sender of this command refuses to send environment variables.

IAC DO ENVIRON

The sender of this command is willing to receive environment variables.

IAC DONT ENVIRON

The sender of this command refuses to accept environment variables.

IAC SB ENVIRON SEND [type ... [type ... [...]]] IAC SE

The sender of this command requests that the remote side send its environment variables. The "type" may be either VAR or USERVAR, to indicate either well known or user variable names. Only the side that is DO ENVIRON may initiate a SEND command. If a list of variables is specified, then only those variables should be sent. If no list is specified, then the default environment, of both well known and user defined variables, should be sent. If one of the variables has no name, then all the variables of that type (well known or user defined) in the default environment should be sent.

IAC SB ENVIRON IS type ... [VALUE ...] [type ... [VALUE ...] [...]] IAC SE

The sender of this command is sending environment variables. This command is sent in response to a SEND request. Only the side that is WILL ENVIRON may send an IS command. The "type"/VALUE pairs must be returned in the same order as the SEND request specified them, and there must be a response for each "type ..." explicitly requested. The "type" will be VAR or USERVAR. Multiple environment variables may be sent. The characters following a "type" up to the next "type" or VALUE specify the variable name. The characters following a VALUE up to the next "type" specify the value of the variable. If a "type" is not followed by a VALUE (e.g., by another VAR, USERVAR, or IAC SE) then that variable is undefined. If a VALUE is immediately followed by a "type" or IAC, then the variable is defined, but has no value. If an IAC is contained between the IS and the IAC SE, it must be sent as IAC IAC. If a

variable or a value contains a VAR, it must be sent as ESC VAR.

If a variable or a value contains a USERVAR, it must be sent as ESC USERVAR. If a variable or a value contains a VALUE, it must be sent as ESC VALUE. If a variable or a value contains an ESC, it must be sent as ESC ESC.

```
IAC SB ENVIRON INFO type ... [ VALUE ... ] [ type ... [ VALUE ... ] [
... ] ] IAC SE
```

The sender of this command is sending information about environment variables that have changed. It is identical to the IS command, except that the command is INFO instead of IS. Only the side that is WILL ENVIRON may send an INFO command. The INFO command is not to be used to send initial information; the SEND/IS sequence is to be used for that. The INFO command is to be used to propagate changes in environment variables, and may be spontaneously generated.

3. Default Specification

The default specification for this option is

```
WONT ENVIRON
DONT ENVIRON
```

meaning there will not be any exchange of environment information.

4. Motivation

Many operating systems have startup information and environment variables that contain information that should be propagated to remote machines when Telnet connections are established. Rather than create a new Telnet option each time someone comes up with some new information that they need propagated through a Telnet session, but that the Telnet session itself doesn't really need to know about, this generic information option can be used.

5. Well Known Variables

USER	This variable is used to transmit the user or account name that the client wishes to log into on the remote system. The format of the value the USER variable is system dependent, as determined by the remote system.
JOB	This variable is used to transmit the job ID that the client wishes to use when logging into the remote system. The format of the value the JOB variable is system dependent, as determined by the remote system.

ACCT This variable is used to transmit the account ID that the

Telnet Working Group

Expires January 1993

[Page 3]

client wishes to use when logging into the remote system. The format of the value the ACCT variable is system dependent, as determined by the remote system.

PRINTER This variable is used to identify the default location for printer output. Because there does not currently exist a standard way of naming a printer on a network, the format of this variable is currently undefined.

SYSTEMTYPE This is used to transmit the type of operating system on the system that sends this variable. Its value is identical to the value of the SYSTEM (SYST) command in FTP [2]. The format of the value shall have as its first word one of the system names listed in the current version of the Assigned Numbers document [3].

DISPLAY This variable is used to transmit the X display location of the client. The format for the value of the DISPLAY variable is:

`<host>:<dispnum>[.<screennum>]`

This information is identical to the information passed using the Telnet X-DISPLAY-LOCATION option. If both the DISPLAY environment variable, and the X-DISPLAY-LOCATION option[4] are received, and they contain conflicting information, the most recently received information received should be used.

Because it is impossible to anticipate all variables that users may wish to exchange, the USERVAR type is provided to allow users to transmit arbitrary variable/value pairs. The use of an additional type allows implementations to distinguish between values derived by the remote host software and values supplied by the user. Paranoid implementations will most likely treat both types with an equal level of distrust. The results of a name-space collision between a well-known and a user variable are implementation specific.

6. Implementation Rules

WILL and DO are used only at the beginning of the connection to obtain and grant permission for future negotiations.

Once the two hosts have exchanged a WILL and a DO, the sender of the DO ENVIRON is free to request that environment variables be sent. Only the sender of the DO may send requests (IAC SB ENVIRON SEND IAC SE) and only the sender of the WILL may transmit actual environment information (via the IAC SB ENVIRON IS ... IAC SE command). Though this option may be used at anytime throughout the

life of the telnet connection, the exchange of environment informa-

tion will usually happen at the startup of the connection. This is because many operating systems only have mechanisms for propagating environment information at process creation, so the information is needed before the user logs in.

The receiving host is not required to put all variables that it receives into the environment. For example, if the client should send across USERVAR "TERM" VALUE "xterm" as an environment variable, and the `TERMINAL-TYPE` [1] option has already been used to determine the terminal type, the server may safely ignore the TERM variable. Also, some startup information may be used in other ways; for example, the values for "USER", "ACCT" and "PROJ" values might be used to decide which account to log into, and might never be put into the users environment. In general, if the server has already determined the value of an environment variable by some more accurate means, or if it does not understand a variable name, it may ignore the value sent in the ENVIRON option. The server may also prefer to just put all unknown information into the users environment. This is the suggested method of implementation, because it allows the user the most flexibility.

The following is an example of use of the option:

Host1	Host2
IAC DO ENVIRON	
	IAC WILL ENVIRON
[Host1 is now free to request environment information]	
IAC SB ENVIRON SEND VAR "USER"	
VAR "ACCT" VAR USERVAR IAC SE	
[The server has now explicitly asked for the USER and ACCT variables, the default set of well known environment variables, and the default set of user defined variables. Note that the client includes the USER information twice; once because it was explicitly asked for, and once because it is part of the default environment.]	
	IAC SB ENVIRON IS VAR "USER"
	VALUE "joe" VAR "ACCT" VALUE
	"kernel" VAR "USER" VALUE "joe"
	VAR "DISPLAY" VALUE "foo:0.0"
	USERVAR "SHELL" VALUE "/bin/csh"
	IAC SE

It is legal for a client to respond with an empty environment (no data between the IAC SB and IAC SE) when no well-defined or user variables are currently defined. For example:

```
IAC SB ENVIRON IS IAC SE
```


is a valid response to any of the following:

Telnet Working Group

Expires January 1993

[Page 5]

```
IAC SB ENVIRON SEND IAC SE
IAC SB ENVIRON SEND VAR IAC SE
IAC SB ENVIRON SEND USERVAR IAC SE
IAC SB ENVIRON SEND VAR USERVAR IAC SE
```

(The last example is equivalent to the first...)

It is expected that any implementation that supports the Telnet ENVIRON option will support all of this specification.

7. Security Concerns

It is important for an implementor of the ENVIRON option to understand the interaction of setting options and the login/authentication process. Specifically careful analysis should be done to determine which variables are "safe" to set prior to having the client login. An example of a bad choice would be permitting a variable to be changed that allows an intruder to circumvent or compromise the login/authentication program itself.

8. References

- [1] VanBokkelen, J., "Telnet Terminal-Type Option", [RFC 1091](#), FTP Software, Inc., February 1989.
- [2] Postel, J. and J. Reynolds, "File Transfer Protocol (FTP)", [RFC 959](#), ISI, October 1985
- [3] Reynolds, J. and J. Postel, "Assigned Numbers", [RFC 1060](#), ISI, March 1990
- [4] Marcy, G., "Telnet X Display Location Option", [RFC 1096](#), Carnegie Mellon University, March 1989.

Author's Address

David A. Borman, Editor
Cray Research, Inc.
655F Lone Oak Drive
Eagan, MN 55123

Phone: (612) 452-6650

Mailing List: telnet-ietf@CRAY.COM
EMail: dab@CRAY.COM

Chair's Address

The working group can be contacted via the current chair:

Steve Alexander
INTERACTIVE Systems Corporation

1901 North Naper Boulevard

Telnet Working Group

Expires January 1993

[Page 6]

Internet-Draft

Telnet Environment Option

July 1992

Naperville, IL 60563-8895

Phone: (708) 505-9100 x256

EMail: stevea@isc.com

