SIP for Click-To-Dial-Back and Third-Party Control

STATUS OF THIS MEMO

[1](1) Introduction

   SIP can also be used to control calls established by other entities,
   for example, to have a computer control a PBX or a web server ask an
   SCP to initiate a call to a standard telephone (''click-to-dial-
   back''). We refer to the entity initiating the phone call as the
   controller and the PBX or SCP as the PSTN server.

[2](2) Outgoing Call

   The controller sends an INVITE request to the PSTN server. The SIP
   request contains information about the caller and the call, e.g.,
   from a web form. The PSTN server may use this information in
   initiating the call. The telephone number to be called is contained
   in the c (connection) parameter of the SDP body. For example, if the
   subscriber with number 415 555 1200 wants to initiate a call through
   her local PBX to the subscriber at 1-212-555-1234, her SIP client
   issues the following request to the PBX:

```
INVITE sip://1-212-555-1234@pbx.example.com
From: j.doe@example.com
Content-type: application/sdp

v=0
o=user1 53655765 2353687637 IN IP4 128.3.4.5
c=PSTN E.164 +1-415-555-1200
t=0 0
m=audio 0 RTP/AVP 0
```

Camp-on is realized with the SIP Call-Disposition "queue" parameter.

[3](#) Answering Incoming Calls

If a controller receives a SIP call, it may indicate in its 200
response to send the audio to a given telephone number, as indicated
in the previous section. Alternatively, it can include the phone
number in a redirection response, but then it is assumed that further
call control is handled by the phone device, not the controller. It
can also reject the call with the standard SIP codes. Call forwarding
is handled with standard SIP 30x status codes.

```
accept call          200
blind transfer        BYE, with new destination
forward, no anser    408
forward, busy        600
forward call         301 or 302,  Location contains address
```

[4](#) Placing Calls on Hold

The party wishing to place the other party on hold sends an INVITE
for the existing call identifier, with an SDP description indicating
a zero port number for the media types it currently does not wish to
receive. This also allows media-specific hold, e.g., to ask the other
side temporarily not to send video. Music-on-hold is implemented by
asking an RTSP server to play to the IP address (or phone number)
provided in the RTSP SETUP request.

[5](#) Call Parking

A user can send an INVITE to an existing call id and cause it to
move to a new extension. [Alternative: PARK request]

[6](#) Call Transfer

To transfer an existing call blindly, the controller sends a BYE containing a Location header indicating the phone number the call is to be transferred to.

For supervised call transfer, the controller initiates a call to the destination of the call, placing the existing call on hold. It then sends a BYE, as above, for the first call. The PBX can transfer back the call to the first destination if the call transfer fails.

[7](#) Configuring the Local PBX

A controller can control a PBX by issuing a REGISTER request with call-handling specification. This call-handling specification can be in a number of programming languages and formats, including a simple list of parameters as a text/parameter. Table 1 lists the parameters currently defined. The REGISTER response returns the current configuration. [TBD: Could use GET_PARAMETER and SET_PARAMETER instead.]

Examples:

autoanswer: on
callsparked: 5
forward_busy: +1-415-555-1234
forward_all: off

autoanswer   on, off
autoanswerspk   on, off
callsparked   integer

Table 1: Configuring PBX behavior using SIP

Table 2: Parameters