

TN3270E Working Group

INTERNET DRAFT: <draft-ietf-tn3270e-tn3270-mib-04.txt>

Kenneth White

Expiration Date: May, 1998

IBM Corp.

November 1997

**Base Definitions of Managed Objects for
TN3270E Using SMIv2**

<draft-ietf-tn3270e-tn3270-mib-04.txt>

Status of this Memo

This document is an Internet Draft. Internet Drafts are working documents of the Internet Engineering Task Force (IETF), its Areas, and its Working Groups. Note that other groups may also distribute working documents as Internet Drafts.

Internet Drafts are draft documents valid for a maximum of six months. Internet Drafts may be updated, replaced, or obsoleted by other documents at any time. It is not appropriate to use Internet Drafts as reference material or to cite them other than as a "working draft" or "work in progress."

Please check the I-D abstract listing contained in each Internet Draft directory to learn the current status of this or any Internet Draft. Distribution of this document is unlimited.

Abstract

The purpose of this memo is to define a Management Information Base (MIB) for configuring and managing TN3270E Servers.

The MIB defined by this memo is intended to provide generic support for both Host and Gateway TN3270E server implementations. It is the intent that the MIB defined herein be extended by subsequent memos to provide non-generic configuration support and to enable TN3270E Response Time Collection.

It is the intent of this MIB to fully adhere to all prerequisite MIBs unless explicitly stated. Deviations will be documented in corresponding conformance statements. The specification of this MIB will utilize the Structure of Management Information (SMI) for Version 2 of the Simple Network Management Protocol Version (refer to [RFC1902](#), reference [1]).

Table of Contents

1.0 Introduction.....	2
2.0 The SNMPv2 Network Management Framework.....	2
2.1 Object Definitions.....	3
3.0 Structure of the MIB.....	3
3.1 TN3270E Server Control.....	4
3.1.1 tn3270eSrvrConfTable.....	4
3.1.2 tn3270eSrvrPortTable.....	5
3.1.3 tn3270eSrvrStatsTable.....	5
3.2 TN3270E Server Resource Configuration.....	6
3.3 Resource/Client Address Mappings.....	6
3.3.1 tn3270eSnaMapTable.....	6
3.3.2 tn3270eResMapTable.....	6
3.3.3 TCP Connection Table Additions.....	7
4.0 Definitions.....	7
5.0 Security Considerations.....	40
6.0 Acknowledgments.....	40
7.0 References.....	41
8.0 Authors' Address.....	42

[1.](#) **Introduction**

This document is a product of the TN3270E Working Group. Its purpose is to define a MIB module for extending the traditional MIBs supported by a TCP/IP implementation for configuration and management of TN3270E servers.

[2.](#) **The SNMPv2 Network Management Framework**

The SNMP Network Management Framework presently consists of three major components. They are:

- o the SMI, described in [RFC 1902](#) [1], - the mechanisms used for describing and naming objects for the purpose of management.
- o the MIB-II, STD 17, [RFC 1213](#) [5], - the core set of managed objects for the Internet suite of protocols.
- o the protocol, [RFC 1157](#) [9] and/or [RFC 1905](#) [7] - the protocol for accessing managed information.

Textual conventions are defined in [RFC 1903](#) [6], and conformance statements are defined in [RFC 1904](#) [8].

The Framework permits new objects to be defined for the purpose of experimentation and evaluation.

Expires May 1998

[Page 2]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

This memo specifies a MIB module that is compliant to the SNMPv2 SMI. A semantically identical MIB conforming to the SNMPv1 SMI can be produced through the appropriate translation.

2.1. Object Definitions

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. Objects in the MIB are defined using the subset of Abstract Syntax Notation One (ASN.1) defined in the SMI. In particular, each object object type is named by an OBJECT IDENTIFIER, an administratively assigned name. The object type together with an object instance serves to uniquely identify a specific instantiation of the object. For human convenience, we often use a textual string, termed the descriptor, to refer to the object type.

3. Structure of the MIB

The TN3270E-MIB is split into the following components:

- o TN3270E Server Control
- o TN3270E Server Resource Configuration
- o Resource/Client Address Mappings

The TN3270E-MIB is defined primarily for TN3270E servers. This memo does not explicitly address use of the MIB by TN3270 servers that do not support the TN3270E protocol. Although a significant number of the objects do apply in the TN3270-only case, the case was not addressed since it is unlikely that a TN3270-only server would implement this MIB.

The SYSAPPL-MIB, reference [[12](#)], is a prerequisite for the TN3270E-

MIB, so that the `Utf8String` Textual Convention (TC) can be imported. This TC, which is used for some MIB objects containing textual information, enables internationalization of text strings, whereas the `DisplayString` TC does not.

The MIB defined by this memo handles both IPv4 and IPv6 addressing. Two Textual Conventions, `Tn3270eAddrType` and `Tn3270eTAddress`, are defined for this purpose. `Tn3270eTAddress` is essentially equivalent to `TAddress`, defined by [RFC 1903](#). The difference is that `Tn3270eTAddress` allows a null-length octet string, while `TAddress` doesn't. Allowing a null IP Address is important, since in places `Tn3270eTAddress` object values are used as a component of an object instance, and need not actually contain an IP Address. In general, use

Expires May 1998

[Page 3]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

of `Tn3270eTAddress` replaces the prior use of `IpAddress` to represent IP Addresses.

`Tn3270eAddrType` is functionally equivalent to the `TDomain` TC, also defined by [RFC 1903](#). `TDomain` uses an OID to identify the contents of a `TAddress` object. `Tn3270eAddrType` was chosen over `TDomain` because, with a SYNTAX of `Unsigned32` (enumeration type), it is much simpler than an OID to specify in an instance identifier.

3.1. TN3270E Server Control

This group of objects provides for TN3270E server configuration, and consists of:

- o `tn3270eSrvrConfTable`
- o `tn3270eSrvrPortTable`
- o `tn3270eSrvrStatsTable`

3.1.1. tn3270eSrvrConfTable

The `tn3270eSrvrConfTable` contains a set of objects primarily for configuring and managing a TN3270E server. As with most of the other tables in the TN3270E-MIB, this table is indexed by an unsigned integer, `tn3270eSrvrConfIndex`. This primary index element enables

support of multiple TN3270E servers on the same host. Within a host, tn3270eSrvrConfIndex values must be unique, and need not be contiguous; otherwise these values are implementation-dependent.

An earlier version of this memo had used the local IP Address associated with a TN3270E server along with tn3270eSrvrConfIndex as the primary indexes into most of its tables. Use of a local IP Address was thought to enable use of these tables by management applications. This approach was dropped, since it introduces a level of complexity into MIB table indexing for little actual benefit.

tn3270eSrvrConfInactivityTimer defines the inactivity period for TN3270 and TN3270E Sessions. tn3270eSrvrConfSessionTermState defines how a session should be terminated. The three objects:

- o tn3270eSrvrConfActivityCheck
- o tn3270eSrvrConfActivityTimeout
- o tn3270eSrvrConfActivityInterval

define the parameters for performing the "Telnet Timing Mark Option" as defined by [RFC 860](#) [3]. The object tn3270eSrvrConfActivityCheck is defined to enable selection of either a NOP command or a TIMEMARK

Expires May 1998

[Page 4]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

command. Sending a NOP command results in less overhead than a TIMEMARK command, since a client doesn't send a reply.

The objects tn3270eSrvrConfAdminStatus and tn3270eSrvrConfOperStatus enable remote starting and stopping of a TN3270E server. tn3270eSrvrConfFunctionsSupported indicates which of the TN3270 and TN3270E options a server supports. The object tn3270eSrvrConfSessionTermState defines as a global option the processing steps that a TN3270E server should perform when a TN3270E session terminates with respect to the associated TCP connection. The object tn3270eSrvrConfSrvrType indicates whether the TN3270E server represented by the tn3270eSrvrConfEntry is a host or a gateway server. The object tn3270eSrvrConfContact provides a scratch pad area for a TN3270E server administrator to store information for later retrieval. The object tn3270eSrvrConfRowStatus provides the capability to perform remote creation and deletion operations on this table.

3.1.2. tn3270eSrvrPortTable

The tn3270eSrvrPortTable exists in order to assign and retrieve the local TCP ports associated with a TN3270E server, since some TN3270E server implementations support multiple local ports. A tn3270eSrvrPortEntry is indexed by:

- o tn3270eSrvrConfIndex
- o tn3270eSrvrConfPort
- o tn3270eSrvrConfPortAddrType
- o tn3270eSrvrConfPortAddress

Certain TN3270E server implementations restrict a local TCP port to a particular local IP Address, instead of allowing connections for any local IP Address to occur via the port. tn3270eSrvrConfPortAddrType and tn3270eSrvrConfPortAddress allow this restriction to be represented in the MIB. A TN3270E server that doesn't restrict connections over a port to a local IP Address should use the value 'unknown(0)' for tn3270eSrvrConfPortAddrType, and a null octet string for tn3270eSrvrConfPortAddress.

3.1.3. tn3270eSrvrStatsTable

The tn3270eSrvrStatsTable defines a series of objects used to provide general statistics on the use of a TN3270E server.

Expires May 1998

[Page 5]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

3.2. TN3270E Server Resource Configuration

The TN3270E Server Resource Configuration collection of objects consists of three tables:

- o tn3270eClientGroupTable
- o tn3270eResPoolTable
- o tn3270eClientResMapTable

`tn3270eClientGroupTable` and `tn3270eResPoolTable` enable implementations to define groupings of both client addresses and resource pools for mapping client addresses to resources. The mapping of a client group to a resource pool is enabled via the `tn3270eClientResMapTable`.

3.3. Resource/Client Address Mappings

Three tables are defined by this memo to enable mapping of resource names to client addresses, and client addresses to resource names:

- o `tn3270eSnaMapTable`
- o `tn3270eResMapTable`
- o TCP Connection Table Additions

3.3.1. tn3270eSnaMapTable

The `tn3270eSnaMapTable` is a read-only table that maps a secondary LU's SNA network name to the name by which it is known locally at the TN3270e server. For correlation with data from a SNA network provision is made for representation of the associating primary LU name in a `tn3270eSnaMapEntry`. An entry in this table is created when the Activate LU (ACTLU) request carrying the SNA network name of the SLU is received from the SSCP. The entry is deleted when the SLU is deactivated.

3.3.2. tn3270eResMapTable

The `tn3270eResMapTable` is a read-only table that maps a resource name to a client's address. An entry in this table is created when a TCP connection is received by a TN3270E server and mapped to a resource. The entry is deleted when the resource-to-address association is no longer valid.

3.3.3. TCP Connection Table Additions

The TCP Connection Table is defined by [RFC 2012](#) (Refer to reference 10, TCP-MIB Definitions). Traditionally, the contents of the TCP Connection Table have been implementation-dependent. Its formal definition consists of the following objects:

- o tcpConnState (INTEGER)
- o tcpConnLocalAddress (IpAddress)
- o tcpConnLocalPort (INTEGER)
- o tcpConnRemAddress (IpAddress)
- o tcpConnRemPort (INTEGER)

It is indexed by: tcpConnLocalAddress, tcpConnLocalPort, tcpConnRemAddress, and tcpConnRemPort.

The tn3270eTcpConnTable contains objects for keeping a list of the current set of TN3270 and TN3270E sessions at a TN3270E server. The relationship between the tcpConnTable and the Tn3270eTcpConnTable is not one-to-one, since the tn3270eTcpConnTable contains information pertaining only to TN3270(E) sessions.

The tn3270eTcpConnTable has a different indexing structure from that of the tcpConnTable. Instead of using IpAddress objects, Tn3270eTAddress and Tn3270eAddrType object pairs are used to specify client addresses (both local and remote). This enables support of IPv6 addresses. In addition, the remote address pair precedes the local address pair in the index clause, in order to enable a GET-NEXT operation using only the remote address pair.

4. Definitions

```
TN3270E-MIB DEFINITIONS ::= BEGIN

IMPORTS
    -- Some MIB Compilers require BITS to be imported from
    -- the SNMPv2-SMI
    MODULE-IDENTITY, OBJECT-TYPE, Unsigned32,
    TimeTicks, InetAddress,
    Counter32, Gauge32, Counter64
        FROM SNMPv2-SMI
    TEXTUAL-CONVENTION, RowStatus
        FROM SNMPv2-TC
    MODULE-COMPLIANCE, OBJECT-GROUP
        FROM SNMPv2-CONF
    snanauMIB
        FROM SNA-NAU-MIB
```

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```
Utf8String
    FROM SYSAPPL-MIB;

tn3270eMIB MODULE-IDENTITY
    LAST-UPDATED "971120000Z" -- November 20, 1997
    ORGANIZATION "TN3270E Working Group"
    CONTACT-INFO
        "Kenneth White (kennethw@vnet.ibm.com)
         IBM Corp."
    DESCRIPTION
        "This module defines a portion of the management
         information base (MIB) for managing TN3270E servers"
 ::= { snanaumIB 8 }

-- Textual Conventions

SnaResourceName ::= TEXTUAL-CONVENTION
    STATUS      current
    DESCRIPTION
        "The textual convention for defining an SNA resource
         name. A fully qualified SNA resource name, consisting of
         a 1 to 8 character network identifier (NetId), a
         period ('.'), and a 1 to 8 character resource name
         (ResName).

The NetId and ResName are constructed from the uppercase
letter 'A' - 'Z' and the numerics '0' - '9', all encoded
in ASCII, with the restriction that the first character
of each must be a letter. Trailing blanks are not allowed.

Earlier versions of SNA permitted three additional
characters in NetIds and ResNames: '#', '@', and '$'.
While this use of these characters has been retired,
a Management Station should still accept them for
backward compatibility.

Note: This Textual Convention is not subject to
internationalization, and does not use the character
encodings used by the Utf8String Textual Convention."
SYNTAX      OCTET STRING (SIZE(0..17))

Tn3270eAddrType ::= TEXTUAL-CONVENTION
    STATUS      current
    DESCRIPTION
```

```

"The textual convention for defining the type of an Client
Address."
SYNTAX      INTEGER {
              unknown(0),

```

Expires May 1998

[Page 8]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```

          ipv4(1),
          ipv6(2)
      }
```

```

Tn3270ResourceType ::= TEXTUAL-CONVENTION
STATUS      current
DESCRIPTION
"The type of resource defined by a resource pool. Refer
to tn3270eResPoolTable."
SYNTAX      INTEGER {
              other(0),
              lu(1),
              printer(2)
      }
```

```

Tn3270eTAddress ::= TEXTUAL-CONVENTION
STATUS      current
DESCRIPTION
"Denotes an Client Address. The type of Client Address is
determined by use of the Tn3270eAddrType Textual
Convention.
```

The length in octets of a Tn3270eTAddress object is:

Tn3270eAddrType	ENUM	
unknown(0)		not known, must look at the actual length of the Tn3270eTAddress OCTET STRING.
ipv4(1)		4 OCTETS
ipv6(2)		16 OCTETS

This textual convention is similar to the TAddress TC
defined by [RFC1903](#) except that it allows a zero length
OCTET STRING and is not a full transport layer address."

```
SYNTAX      OCTET STRING (SIZE (0..255))
```

Tn3270Functions ::= TEXTUAL-CONVENTION
STATUS current
DESCRIPTION
"This textual convention is intended to reflect the current set of TN3270 and TN3270E functions that can be negotiated between a server and its client:

[RFC856](#)

transmitBinary The sender of this command REQUESTS permission to begin transmitting, or confirms that it will now begin transmitting characters which are to be interpreted

Expires May 1998

[Page 9]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

as 8 bits of binary data by the receiver of the data.

[RFC820](#)

timeMark The sender of this command REQUESTS that the receiver of this command return a WILL TIMING-MARK in the data stream at the 'appropriate place' ...

[RFC885](#)

endOfRecord The sender of this command requests permission to begin transmission of the Telnet END-OF-RECORD (EOR) code when transmitting data characters, or the sender of this command confirms it will now begin transmission of EORs with transmitted data characters.

[RFC1091](#)

terminalType Sender is willing to send terminal type information in a subsequent sub-negotiation.

[RFC1041](#)

tn3270Regime Sender is willing to send list of supported 3270 Regimes in a subsequent sub-negotiation.

[RFC1647](#)

scsCtlCodes (Printer sessions only). Allows the use of the SNA Character Stream (SCS) and SCS control codes on the session. SCS is used with LU type 1 SNA sessions.

dataStreamCtl	(Printer sessions only). Allows the use of the standard 3270 data stream. This corresponds to LU type 3 SNA sessions.
responses	Provides support for positive and negative response handling. Allows the server to reflect to the client any and all definite, exception, and no response requests sent by the host application.
bindImage	Allows the server to send the SNA Bind image and Unbind notification to the client.
sysreq	Allows the client and server to emulate some (or all, depending on the server) of the functions of the SYSREQ key in an SNA environment."
SYNTAX	BITS {
	transmitBinary(0), -- rfc856
	timemark(1), -- rfc860
	endOfRecord(2), -- rfc885
	terminalType(3), -- rfc1091
	tn3270Regime(4), -- rfc1041
	scsCtlCodes(5), -- rfc1647

Expires May 1998

[Page 10]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```

dataStreamCtl(6), -- rfc1647
responses(7), -- rfc1647
bindImage(8), -- rfc1647
sysreq(9) -- rfc1647
}

```

```

Tn3270DeviceTypes ::= TEXTUAL-CONVENTION
STATUS      current
DESCRIPTION
"This textual convention defines the list of device types
that can be set as defined by RFC 1647."
SYNTAX      INTEGER { -- terminals
    unknown(0),
    ibm3278d2(1), -- (24 row x 80 col display)
    ibm3278d2E(2), -- (24 row x 80 col display)
    ibm3278d3(3), -- (32 row x 80 col display)
    ibm3278d3E(4), -- (32 row x 80 col display)
}

```

```

        ibm3278d4(5),      -- (43 row x 80 col display)
        ibm3278d4E(6),    -- (43 row x 80 col display)
        ibm3278d5(7),    -- (27 row x 132 col display)
        ibm3278d5E(8),   -- (27 row x 132 col display)
        ibmDynamic(9),    -- (no pre-defined display size)
        ibm3287d1(10)    -- printers
    }

```

-- Top-level structure of the MIB

```

tn3270eNotifications OBJECT IDENTIFIER ::= { tn3270eMIB 0 }
tn3270eObjects        OBJECT IDENTIFIER ::= { tn3270eMIB 1 }
tn3270eConformance    OBJECT IDENTIFIER ::= { tn3270eMIB 3 }

```

-- MIB Objects

```

tn3270eSrvrConfTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF Tn3270eSrvrConfEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "This table defines the configuration elements for
        TN3270E Servers. The number of entries in this table
        is expected to vary depending on the location of the
        table. A particular TN3270E server is expected to
        have a single entry. Modeling of the configuration
        elements as a table allows multiple
        TN3270E Servers to exist at the same host."
    ::= { tn3270eObjects 1 }

```

tn3270eSrvrConfEntry OBJECT-TYPE

Expires May 1998

[Page 11]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```

SYNTAX      Tn3270eSrvrConfEntry
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
    "Definition of the configuration elements for a single
    TN3270E server."
INDEX      { tn3270eSrvrConfIndex }
 ::= { tn3270eSrvrConfTable 1 }

```

```

Tn3270eSrvrConfEntry ::= SEQUENCE {
    tn3270eSrvrConfIndex          Unsigned32,
    tn3270eSrvrConfInactivityTimeout Unsigned32,
    tn3270eSrvrConfActivityCheck   INTEGER,
    tn3270eSrvrConfActivityTimeout Unsigned32,
    tn3270eSrvrConfActivityInterval Unsigned32,
    tn3270eSrvrFunctionsSupported   Tn3270Functions,
    tn3270eSrvrConfAdminStatus     INTEGER,
    tn3270eSrvrConfOperStatus      INTEGER,
    tn3270eSrvrConfSessionTermState INTEGER,
    tn3270eSrvrConfSrvrType        INTEGER,
    tn3270eSrvrConfContact         Utf8String,
    tn3270eSrvrConfRowStatus       RowStatus
}

tn3270eSrvrConfIndex OBJECT-TYPE
    SYNTAX      Unsigned32
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "Indicates the instance of a TN3270E server that
         exists at an IP Host. Assignments of tn3270eSrvrConfIndex
         values need not be continuous and is implementation
         dependent. Within a host, assignment of
         tn3270eSrvrConfIndex values must be unique."
    ::= { tn3270eSrvrConfEntry 1 }

tn3270eSrvrConfInactivityTimeout OBJECT-TYPE
    SYNTAX      Unsigned32 (0..99999999)
    UNITS "seconds"
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION
        "The inactivity time-out specified in seconds. When a
         connection has been inactive for the number of seconds
         specified by this object it is closed. The default of
         0 means no inactivity time-out."
    DEFVAL { 0 }
    ::= { tn3270eSrvrConfEntry 2 }

```

```

tn3270eSrvrConfActivityCheck OBJECT-TYPE
  SYNTAX      INTEGER {
                noCheck(0),
                timeMark(1),
                nop(2)
            }
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION
    "This object is intended to enable either timemark or
     nop processing."
  DEFVAL { noCheck }
  ::= { tn3270eSrvrConfEntry 3 }

tn3270eSrvrConfActivityTimeout OBJECT-TYPE
  SYNTAX      Unsigned32 (1..99999999)
  UNITS "seconds"
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION
    "The TIMEMARK or NOP processing time-out specified in seconds.
     Note that a value of 0 is not allowed for this object since
     the function that uses this object relies on
     tn3270eSrvrConfActivityCheck for function enablement."
  DEFVAL { 600 }    -- 10 minutes
  ::= { tn3270eSrvrConfEntry 4 }

tn3270eSrvrConfActivityInterval OBJECT-TYPE
  SYNTAX      Unsigned32 (1..99999999)
  UNITS "seconds"
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION
    "The scan interval to be used by a TN3270E server.
     TIMEMARK or NOP processing scans the Telnet sessions
     on the interval provided by this object looking for
     sessions that have been idle for more than the value
     provided by tn3270eSrvrConfActivityTimeout.
     Note that a value of 0 is not allowed for this object since
     the function that uses this object relies on
     tn3270eSrvrConfActivityCheck for function enablement."
  DEFVAL { 120 }    -- 2 minutes
  ::= { tn3270eSrvrConfEntry 5 }

tn3270eSrvrFunctionsSupported OBJECT-TYPE
  SYNTAX      Tn3270Functions
  MAX-ACCESS  read-only
  STATUS      current

```

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

DESCRIPTION

"This object indicates the functions supported by a TN3270E server."
DEFVAL { { scsCtlCodes, dataStreamCtl,
 responses, bindImage, sysreq } }
 ::= { tn3270eSrvrConfEntry 6 }

tn3270eSrvrConfAdminStatus OBJECT-TYPE

SYNTAX INTEGER {
 up(1),
 down(2),
 stopImmediate(3)
}

MAX-ACCESS read-create

STATUS current

DESCRIPTION

"The desired state of the TN3270E server:

up(1) - Activate a TN3270E server.
down(2) - Informs the associating TN3270E server
 to gracefully terminate its processing.
stopImmediate(3) - Informs the associating TN3270E server
 to terminate immediately.

Implementation as to the exact semantics of either down(2)
or stopImmediate(3) processing is left as implementation
dependent. A TN3270E server that does not distinguish
between down or stopImmediate transitions should not
support stopImmediate."

::= { tn3270eSrvrConfEntry 7 }

tn3270eSrvrConfOperStatus OBJECT-TYPE

SYNTAX INTEGER {
 up(1),
 down(2)
}

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"The current operational state of a TN3270E server:

```
    up(1) - The corresponding TN3270E server is active.  
    down(2) - The corresponding TN3270E server is inactive."  
 ::= { tn3270eSrvrConfEntry 8 }
```

```
tn3270eSrvrConfSessionTermState OBJECT-TYPE  
SYNTAX  INTEGER {  
            terminate(1),
```

Expires May 1998

[Page 14]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```
        luSessionPend(2),  
        queueSession(3)  
    }  
MAX-ACCESS  read-create  
STATUS      current  
DESCRIPTION  
"The current state for determining what a TN3270E server  
should do when a TN3270 Session terminates:  
  
terminate(1)    => Terminate TCP connection.  
luSessionPend(2) => Do not drop the TCP Connection  
                    associated with a client when their  
                    TN3270 Session ends. Processing should  
                    redrive session initialization as if the  
                    client was first connecting.  
queueSession(3)  => QUEUESSESSION deals with CLSDST-Pass.  
                    An example is the easiest explanation.  
                    Assume APPL1 does a CLSDST-Pass  
                    to APPL2. Then the client logs off APPL  
                    Without QUEUESSESSION the connection  
                    would now be broken. With QUEUESSESSION  
                    the TN3270E server keeps the LU around  
                    after getting the APPL2 unbind waiting  
                    for a bind from APPL1."  
DEFVAL { terminate }  
 ::= { tn3270eSrvrConfEntry 9 }
```

```
tn3270eSrvrConfSrvrType OBJECT-TYPE  
SYNTAX  INTEGER {  
            unknown(0),  
            host(1),  
            gateway(2)
```

```

        }
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "This object indicates the type of TN3270E server.
     The existence of MIB tables and objects that will be
     defined by follow-on MIBs may be predicated on whether the
     TN3270E server can be local to the same host as a
     Target Application (host(1)) or will always be remote
     (gateway(2))."
 ::= { tn3270eSrvrConfEntry 10 }

```

```

tn3270eSrvrConfContact OBJECT-TYPE
SYNTAX      Utf8String (SIZE(0..255))
MAX-ACCESS  read-create
STATUS      current

```

Expires May 1998

[Page 15]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```

DESCRIPTION
    "This object provides a scratch pad for a TN3270E server
     administrator for storing information for later retrieval."
 ::= { tn3270eSrvrConfEntry 11 }

```

```

tn3270eSrvrConfRowStatus OBJECT-TYPE
SYNTAX      RowStatus
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION
    "This object allows entries to be created and deleted in the
     tn3270eSrvrConfTable.

     An entry in this table is deleted by setting this object
     to destroy(6)."

```

REFERENCE

"[RFC 1903](#), 'Textual Conventions for version 2 of the Simple
Network Management Protocol (SNMPv2).'"

```

 ::= { tn3270eSrvrConfEntry 12 }

```

```

tn3270eSrvrPortTable OBJECT-TYPE
SYNTAX      SEQUENCE OF Tn3270eSrvrPortEntry
MAX-ACCESS  not-accessible

```

```

STATUS      current
DESCRIPTION
    "This table defines the TCP ports associated with TN3270E
    Servers."
::= { tn3270eObjects 2 }

tn3270eSrvrPortEntry OBJECT-TYPE
    SYNTAX      Tn3270eSrvrPortEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "Definition of a single TCP port assignment to a
        TN3270E server."
    INDEX      {
        tn3270eSrvrConfIndex,
        tn3270eSrvrPort,
        tn3270eSrvrPortAddrType,
        tn3270eSrvrPortAddress
    }
::= { tn3270eSrvrPortTable 1 }

Tn3270eSrvrPortEntry ::= SEQUENCE {
    tn3270eSrvrPort          Unsigned32,
    tn3270eSrvrPortAddrType   Tn3270eAddrType,
    tn3270eSrvrPortAddress    Tn3270eTAddress,
}

```

Expires May 1998

[Page 16]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```

    tn3270eSrvrPortRowStatus      RowStatus
}

tn3270eSrvrPort OBJECT-TYPE
    SYNTAX      Unsigned32 (0..65535)
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "Indicates a port assigned to a server."
::= { tn3270eSrvrPortEntry 1 }

```

```

tn3270eSrvrPortAddrType OBJECT-TYPE
    SYNTAX      Tn3270eAddrType
    MAX-ACCESS  not-accessible

```

```

STATUS      current
DESCRIPTION
    "Indicates the type of the Client Address represented in
     tn3270eSrvrPortAddress."
 ::= { tn3270eSrvrPortEntry 2 }

tn3270eSrvrPortAddress OBJECT-TYPE
SYNTAX      Tn3270eTAddress
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
    "The Client Address associated with a TN3270E server port.
     tn3270eClientGroupAddrType indicates the address type
     (ipv4 or ipv6 for example)."
 ::= { tn3270eSrvrPortEntry 3 }

tn3270eSrvrPortRowStatus OBJECT-TYPE
SYNTAX      RowStatus
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION
    "This object allows entries to be created and deleted in the
     tn3270eSrvrPortTable.

     An entry in this table is deleted by setting this object
     to destroy(6)."
REFERENCE
    "RFC 1903, 'Textual Conventions for version 2 of the Simple
     Network Management Protocol (SNMPv2).'"
 ::= { tn3270eSrvrPortEntry 4 }

tn3270eSrvrStatsTable OBJECT-TYPE
SYNTAX      SEQUENCE OF Tn3270eSrvrStatsEntry
MAX-ACCESS  not-accessible

```

Expires May 1998

[Page 17]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```

STATUS      current
DESCRIPTION
    "This table defines a set of statistics concerning
     global TN3270E server performance."
 ::= { tn3270eObjects 3 }

```

```

tn3270eSrvrStatsEntry OBJECT-TYPE
    SYNTAX      Tn3270eSrvrStatsEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "Collection of a set of statistic objects for a single
         TN3270 server. An entry can be global with respect to
         a single TN3270E server or be specified at a port level.
         Refer to the text description for tn3270eSrvrStatsPort.

```

It is possible that a TN3270E server implementation may not be structured to support resource usage on a port basis but provide statistics via an entry in this table for each port. The recommended approach for this is to provide a global entry (a value of 0 for tn3270eSrvrStatsPort) with:

```

tn3270eSrvrStatsMaxLus
tn3270eSrvrStatsMaxLus
tn3270eSrvrStatsLusInUse
tn3270eSrvrStatsSpareLus
tn3270eSrvrStatsMaxPtrs
tn3270eSrvrStatsPtrsInUse
tn3270eSrvrStatsSparePtrs

        set at this layer but set to zero at the port layer."
INDEX      { tn3270eSrvrConfIndex, tn3270eSrvrStatsPort }
 ::= { tn3270eSrvrStatsTable 1 }

```

```

Tn3270eSrvrStatsEntry ::= SEQUENCE {
    tn3270eSrvrStatsPort          Unsigned32,
    tn3270eSrvrStatsUpTime        TimeTicks,
    tn3270eSrvrStatsMaxLus        Unsigned32,
    tn3270eSrvrStatsLusInUse      Gauge32,
    tn3270eSrvrStatsSpareLus      Gauge32,
    tn3270eSrvrStatsMaxPtrs       Unsigned32,
    tn3270eSrvrStatsPtrsInUse     Gauge32,
    tn3270eSrvrStatsSparePtrs     Gauge32,
    tn3270eSrvrStatsConnectsIn   Counter32,
    tn3270eSrvrStatsConnRejects  Counter32,
    tn3270eSrvrStatsDisconnects Counter32,
    tn3270eSrvrStatsOctetsIn     Counter64,

```

```
tn3270eSrvrStatsOctetsInLow      Counter32,
tn3270eSrvrStatsOctetsOut       Counter64,
tn3270eSrvrStatsOctetsOutLow    Counter32
}

tn3270eSrvrStatsPort OBJECT-TYPE
    SYNTAX      Unsigned32 (0..65535)
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "Indicates the port that the corresponding statistics are
         for. Implementation of collection of these statistics
         on a port basis is not mandatory. An implementation may
         limit itself to keeping this data on a global basis by
         using a value of 0."
    ::= { tn3270eSrvrStatsEntry 1 }

tn3270eSrvrStatsUpTime OBJECT-TYPE
    SYNTAX      TimeTicks
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "Indicates when either usage of a associating port becomes
         active (tn3270eSrvrStatsPort non-zero) or if the entry
         is being kept on a global basis the time that the TN3270E
         server becomes active. The value of this object does not
         get reset based on port usage status changes or changes
         to tn3270eSrvrConfOperStatus."
    ::= { tn3270eSrvrStatsEntry 2 }

tn3270eSrvrStatsMaxLus OBJECT-TYPE
    SYNTAX      Unsigned32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "Indicates the maximum number of LUs for use by a
         TN3270E server. The granularity of this data can be
         either global (corresponding tn3270eSrvrStatsPort index
         equal to 0) or on a port basis."
    ::= { tn3270eSrvrStatsEntry 3 }

tn3270eSrvrStatsLusInUse OBJECT-TYPE
    SYNTAX      Gauge32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "Indicates the current number of LUs in use by a
```

TN3270E server. The granularity of this data can be

Expires May 1998

[Page 19]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

either global (corresponding tn3270eSrvrStatsPort index
equal to 0) or on a port basis."
 ::= { tn3270eSrvrStatsEntry 4 }

tn3270eSrvrStatsSpareLus OBJECT-TYPE
SYNTAX Gauge32
MAX-ACCESS read-only
STATUS current
DESCRIPTION
"Indicates the number of free LUs for a particular TN3270E
server. It is possible that the difference between
tn3270eSrvrStatsMaxLus and tn3270eSrvrStatsLusInUse does
not equal tn3270eSrvrStatsSpareLus. An LU may exist
but not be useable by an client connection.
The granularity of this data can be
either global (corresponding tn3270eSrvrStatsPort index
equal to 0) or on a port basis."
 ::= { tn3270eSrvrStatsEntry 5 }

tn3270eSrvrStatsMaxPtrs OBJECT-TYPE
SYNTAX Unsigned32
MAX-ACCESS read-only
STATUS current
DESCRIPTION
"Indicates the maximum number of Printer Resources for
use by a TN3270E server. The granularity of this data
can be either global (corresponding tn3270eSrvrStatsPort
index equal to 0) or on a port basis."
 ::= { tn3270eSrvrStatsEntry 6 }

tn3270eSrvrStatsPtrsInUse OBJECT-TYPE
SYNTAX Gauge32
MAX-ACCESS read-only
STATUS current
DESCRIPTION
"Indicates the current number of Printer Resources in
use by a TN3270E server. The granularity of this data
can be either global (corresponding tn3270eSrvrStatsPort

```
    index equal to 0) or on a port basis."
::= { tn3270eSrvrStatsEntry 7 }

tn3270eSrvrStatsSparePtrs OBJECT-TYPE
SYNTAX      Gauge32
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "Indicates the number of free Printer Resources for a
     particular TN3270E server. It is possible that the
```

Expires May 1998

[Page 20]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```
difference between tn3270eSrvrStatsMaxPtrs and
tn3270eSrvrStatsPtrsInUse does not equal
tn3270eSrvrStatsSparePtrs. A Printer resource may
exist but not be useable by an client connection.
The granularity of this data
can be either global (corresponding tn3270eSrvrStatsPort
index equal to 0) or on a port basis."
::= { tn3270eSrvrStatsEntry 8 }
```

```
tn3270eSrvrStatsConnectsIn OBJECT-TYPE
SYNTAX      Counter32
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "Indicates the number of client connections received by a
     TN3270E server. The granularity of this data
     can be either global (corresponding tn3270eSrvrStatsPort
     index equal to 0) or on a port basis."
::= { tn3270eSrvrStatsEntry 9 }
```

```
tn3270eSrvrStatsConnRejects OBJECT-TYPE
SYNTAX      Counter32
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "Indicates the number of client connections rejected during
     connection setup. An example of this is when no LU or
     Printer resource is available to associate with the
     TCP Connection of an client. The granularity of this data
```

```
can be either global (corresponding tn3270eSrvrStatsPort
index equal to 0) or on a port basis."
 ::= { tn3270eSrvrStatsEntry 10 }

tn3270eSrvrStatsDisconnects OBJECT-TYPE
 SYNTAX      Counter32
 MAX-ACCESS  read-only
 STATUS      current
 DESCRIPTION
 "Indicates the number of client connections disconnected by a
 TN3270E server. The granularity of this data
 can be either global (corresponding tn3270eSrvrStatsPort
 index equal to 0) or on a port basis."
 ::= { tn3270eSrvrStatsEntry 11 }
```

```
tn3270eSrvrStatsOctetsIn OBJECT-TYPE
 SYNTAX      Counter64
 MAX-ACCESS  read-only
 STATUS      current
```

Expires May 1998

[Page 21]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```
DESCRIPTION
 "Indicates the number of octets received from TN3270
 and TN3270E Clients. The granularity
 of this data can be either global (corresponding
 tn3270eSrvrStatsPort index equal to 0) or on a port basis."
 ::= { tn3270eSrvrStatsEntry 12 }
```

```
tn3270eSrvrStatsOctetsInLow OBJECT-TYPE
 SYNTAX      Counter32
 MAX-ACCESS  read-only
 STATUS      current
 DESCRIPTION
 "Low order 32 bits of tn3270eSrvrStatsOctetsIn."
 ::= { tn3270eSrvrStatsEntry 13 }
```

```
tn3270eSrvrStatsOctetsOut OBJECT-TYPE
 SYNTAX      Counter64
 MAX-ACCESS  read-only
 STATUS      current
 DESCRIPTION
```

```
"Indicates the number of octets sent to TN3270  
and TN3270E Clients. The granularity  
of this data can be either global (corresponding  
tn3270eSrvrStatsPort index equal to 0) or on a port basis."  
 ::= { tn3270eSrvrStatsEntry 14 }
```

```
tn3270eSrvrStatsOctetsOutLow OBJECT-TYPE  
SYNTAX      Counter32  
MAX-ACCESS  read-only  
STATUS      current  
DESCRIPTION  
"Low order 32 bits of tn3270eSrvrStatsOctetsOut."  
 ::= { tn3270eSrvrStatsEntry 15 }
```

```
tn3270eClientGroupTable OBJECT-TYPE  
SYNTAX      SEQUENCE OF Tn3270eClientGroupEntry  
MAX-ACCESS  not-accessible  
STATUS      current  
DESCRIPTION  
"This table defines client address groupings for use by a  
TN3270E server."  
 ::= { tn3270eObjects 4 }
```

```
tn3270eClientGroupEntry OBJECT-TYPE  
SYNTAX      Tn3270eClientGroupEntry  
MAX-ACCESS  not-accessible  
STATUS      current  
DESCRIPTION
```

Expires May 1998

[Page 22]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```
"Definition of a single client address entry. All entries with  
the same first two indexes, tn3270eSrvrConfIndex and  
tn3270eClientGroupName, are considered to be in the same  
client group."  
INDEX      { tn3270eSrvrConfIndex,  
             tn3270eClientGroupName,  
             tn3270eClientGroupAddrType,  
             tn3270eClientGroupAddress }  
 ::= { tn3270eClientGroupTable 1 }
```

Tn3270eClientGroupEntry ::= SEQUENCE {

```

tn3270eClientGroupName          Utf8String,
tn3270eClientGroupAddrType     Tn3270eAddrType,
tn3270eClientGroupAddress       Tn3270eTAddress,
tn3270eClientGroupSubnetMask   IpAddress,
tn3270eClientGroupPfxLength    Unsigned32,
tn3270eClientGroupRowStatus    RowStatus }

tn3270eClientGroupName OBJECT-TYPE
SYNTAX      Utf8String (SIZE(1..24))
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
"The name of a client group."
 ::= { tn3270eClientGroupEntry 1 }

tn3270eClientGroupAddrType OBJECT-TYPE
SYNTAX      Tn3270eAddrType
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
"Indicates the type of the address represented in
tn3270eClientGroupAddress."
 ::= { tn3270eClientGroupEntry 2 }

tn3270eClientGroupAddress OBJECT-TYPE
SYNTAX      Tn3270eTAddress
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
"The client address of a member of a client group. The value
of tn3270eClientGroupAddrType indicates the address
type (ipv4 or ipv6 for example)."
 ::= { tn3270eClientGroupEntry 3 }

tn3270eClientGroupSubnetMask OBJECT-TYPE
SYNTAX      IpAddress
MAX-ACCESS  read-create

```

Expires May 1998

[Page 23]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```

STATUS      current
DESCRIPTION

```

```

"The corresponding subnet mask associated with
tn3270eClientGroupAddress. A single IP Address is
represented by having this object contain the value
of 255.255.255.255. This object is valid only if
tn3270eClientGroupAddrType has a value of ipv4(1)."
DEFVAL { 'FFFFFFF'H }
 ::= { tn3270eClientGroupEntry 4 }

tn3270eClientGroupPfxLength OBJECT-TYPE
SYNTAX      Unsigned32 (0..128)
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION
    "The corresponding IPv6 network prefix length. This
     object is valid only if tn3270eClientGroupAddrType
     has a value of ipv6(2)."
DEFVAL { 0 }
 ::= { tn3270eClientGroupEntry 5 }

tn3270eClientGroupRowStatus OBJECT-TYPE
SYNTAX      RowStatus
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION
    "This object allows entries to be created and deleted in the
     tn3270eClientGroupTable.

     An entry in this table is deleted by setting this object
     to destroy(6)."
REFERENCE
    "RFC 1903, 'Textual Conventions for version 2 of the Simple
     Network Management Protocol (SNMPv2).'"
 ::= { tn3270eClientGroupEntry 6 }

tn3270eResPoolTable OBJECT-TYPE
SYNTAX      SEQUENCE OF Tn3270eResPoolEntry
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
    "This table defines resource groupings; the term
     'pool' is used as it is defined by RFC 1647."
 ::= { tn3270eObjects 5 }

tn3270eResPoolEntry OBJECT-TYPE
SYNTAX      Tn3270eResPoolEntry
MAX-ACCESS  not-accessible

```

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```
STATUS      current
DESCRIPTION
    "Definition of a single resource pool member. All entries
     with the same first two indexes, tn3270eSrvrConfIndex and
     tn3270eResPoolName, are considered to be in the same pool."
INDEX  { tn3270eSrvrConfIndex,
          tn3270eResPoolName,
          tn3270eResPoolElementName }
 ::= { tn3270eResPoolTable 1 }

Tn3270eResPoolEntry ::= SEQUENCE {
    tn3270eResPoolName          Utf8String,
    tn3270eResPoolElementName   SnaResourceName,
    tn3270eResPoolElementType   Tn3270ResourceType,
    tn3270eResPoolRowStatus     RowStatus }

tn3270eResPoolName OBJECT-TYPE
    SYNTAX      Utf8String (SIZE(1..24))
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "The name of a resource pool.."
    ::= { tn3270eResPoolEntry 1 }

tn3270eResPoolElementName OBJECT-TYPE
    SYNTAX      SnaResourceName
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "The name of a member of a resource pool."
    ::= { tn3270eResPoolEntry 2 }

tn3270eResPoolElementType OBJECT-TYPE
    SYNTAX      Tn3270ResourceType
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION
        "The type of the entity in a resource pool."
    ::= { tn3270eResPoolEntry 3 }

tn3270eResPoolRowStatus OBJECT-TYPE
    SYNTAX      RowStatus
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION
```

"This object allows entries to be created and deleted in the tn3270eResPoolTable.

Expires May 1998

[Page 25]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

An entry in this table is deleted by setting this object to destroy(6)."

REFERENCE

"[RFC 1903](#), 'Textual Conventions for version 2 of the Simple Network Management Protocol (SNMPv2).'"

::= { tn3270eResPoolEntry 4 }

tn3270eSnaMapTable OBJECT-TYPE

SYNTAX SEQUENCE OF Tn3270eSnaMapEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"This table provide a mapping from the name by which a secondary LU is known in the SNA network to the name by which it is known locally at the TN3270e server. This latter name serves as an index into the tn3270eResPoolTable and the tn3270eResMapTable."

::= { tn3270eObjects 6 }

tn3270eSnaMapEntry OBJECT-TYPE

SYNTAX Tn3270eSnaMapEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"Definition of a single mapping from an SSCP-supplied SLU name to a local SLU name."

INDEX { tn3270eSrvrConfIndex,
 tn3270eSnaMapSscpSuppliedName }
::= { tn3270eSnaMapTable 1 }

Tn3270eSnaMapEntry ::= SEQUENCE {

 tn3270eSnaMapSscpSuppliedName SnaResourceName,

 tn3270eSnaMapLocalName SnaResourceName,

 tn3270eSnaMapPrimaryLuName SnaResourceName }

tn3270eSnaMapSscpSuppliedName OBJECT-TYPE

```
SYNTAX      SnaResourceName
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
    "The name of the secondary LU (SLU) as it is known in the
    SNA network. This name is sent by the SSCP on the
    Activate Logical Unit (ACTLU) request."
 ::= { tn3270eSnaMapEntry 1 }
```

tn3270eSnaMapLocalName OBJECT-TYPE

```
SYNTAX      SnaResourceName
MAX-ACCESS  read-only
```

Expires May 1998

[Page 26]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```
STATUS      current
DESCRIPTION
    "The local name of the secondary LU (SLU)."
 ::= { tn3270eSnaMapEntry 2 }
```

tn3270eSnaMapPrimaryLuName OBJECT-TYPE

```
SYNTAX      SnaResourceName
```

```
MAX-ACCESS  read-only
```

```
STATUS      current
```

```
DESCRIPTION
    "When there is a currently active LU-LU session for this
    connection, this object returns the primary LU (PLU) name
    from the BIND. When there is no active LU-LU session, or
    when the PLU name is unavailable for some other reason,
    this object returns the empty string."
 ::= { tn3270eSnaMapEntry 3 }
```

tn3270eClientResMapTable OBJECT-TYPE

```
SYNTAX      SEQUENCE OF Tn3270eClientResMapEntry
```

```
MAX-ACCESS  not-accessible
```

```
STATUS      current
```

```
DESCRIPTION
```

```
    "This table defines resource pool to client group mappings.
    Since both the resource pool name and client group name
    are included in the index clause of this table, multiple
    resource pools can be assigned to the same client group. This
    enables use of multiple resource pools for use in client to
```

resource mapping. Assigning multiple client Groups to the same resource pool is also allowed, but is not the primary purpose for how the indexing is structured.

Assignment of a resource pool to client group can be restricted based on TCP port. An index value of 0 for tn3270eClientResMapClientPort disables restriction of resource assignment based on client target port selection."
 ::= { tn3270eObjects 7 }

tn3270eClientResMapEntry OBJECT-TYPE
SYNTAX Tn3270eClientResMapEntry
MAX-ACCESS not-accessible
STATUS current
DESCRIPTION
"Definition of a single resource pool to client group mapping."
INDEX { tn3270eSrvrConfIndex,
tn3270eClientResMapPoolName,
tn3270eClientResMapClientGroupName,
tn3270eClientResMapClientPort }

Expires May 1998

[Page 27]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

::= { tn3270eClientResMapTable 1 }

Tn3270eClientResMapEntry ::= SEQUENCE {
tn3270eClientResMapPoolName Utf8String,
tn3270eClientResMapClientGroupName Utf8String,
tn3270eClientResMapClientPort Unsigned32,
tn3270eClientResMapRowStatus RowStatus }

tn3270eClientResMapPoolName OBJECT-TYPE
SYNTAX Utf8String (SIZE(1..24))
MAX-ACCESS not-accessible
STATUS current
DESCRIPTION
"The name of a resource pool."
 ::= { tn3270eClientResMapEntry 1 }

tn3270eClientResMapClientGroupName OBJECT-TYPE
SYNTAX Utf8String (SIZE(1..24))

```

MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
    "The name of the client group that is mapped to a
     resource pool."
 ::= { tn3270eClientResMapEntry 2 }

tn3270eClientResMapClientPort OBJECT-TYPE
SYNTAX      Unsigned32 (0..65535)
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
    "The port to restrict a resource pool to a client group
     mapping. A value of 0 for this objects implies that
     the mapping is not restricted."
 ::= { tn3270eClientResMapEntry 3 }

tn3270eClientResMapRowStatus OBJECT-TYPE
SYNTAX      RowStatus
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION
    "This object allows entries to be created and deleted in the
     tn3270eClientResMapTable.

    An entry in this table is deleted by setting this object
     to destroy(6)."
REFERENCE
    "RFC 1903, 'Textual Conventions for version 2 of the Simple
     Network Management Protocol (SNMPv2).'"

```

Expires May 1998

[Page 28]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```

 ::= { tn3270eClientResMapEntry 4 }

tn3270eResMapTable OBJECT-TYPE
SYNTAX      SEQUENCE OF Tn3270eResMapEntry
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
    "This table defines the actual mapping of a resource to
     a client Address."

```

```
::= { tn3270eObjects 8 }

tn3270eResMapEntry OBJECT-TYPE
    SYNTAX      Tn3270eResMapEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "Definition of the mapping of a Resource Element to
         a client Address."
    INDEX   { tn3270eSrvrConfIndex,
              tn3270eResMapElementName }
::= { tn3270eResMapTable 1 }
```

```
Tn3270eResMapEntry ::= SEQUENCE {
    tn3270eResMapElementName      SnaResourceName,
    tn3270eResMapAddrType        Tn3270eAddrType,
    tn3270eResMapAddress         Tn3270eTAddress,
    tn3270eResMapPort            Unsigned32,
    tn3270eResMapElementType     Tn3270ResourceType,
    tn3270eResMapSscpSuppliedName SnaResourceName }
```

```
tn3270eResMapElementName OBJECT-TYPE
    SYNTAX      SnaResourceName
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "The name of a resource element. This is the name by
         which the server implementing this table knows the
         resource. It may be different from the name by which
         the resource is known in the SNA network. In this case
         the name by which the resource is known in the SNA
         network is returned in the tn3270eResMapSscpSuppliedName
         object."
::= { tn3270eResMapEntry 1 }
```

```
tn3270eResMapAddrType OBJECT-TYPE
    SYNTAX      Tn3270eAddrType
    MAX-ACCESS  read-only
    STATUS      current
```

```

DESCRIPTION
    "Indicates the type of the client Address represented in
     tn3270eResMapAddress."
 ::= { tn3270eResMapEntry 2 }

tn3270eResMapAddress OBJECT-TYPE
    SYNTAX      Tn3270eTAddress
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "A client address."
 ::= { tn3270eResMapEntry 3 }

tn3270eResMapPort OBJECT-TYPE
    SYNTAX      Unsigned32 (0..65535)
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "A client Port."
 ::= { tn3270eResMapEntry 4 }

tn3270eResMapElementType OBJECT-TYPE
    SYNTAX      Tn3270ResourceType
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The type of the associating resource element."
 ::= { tn3270eResMapEntry 5 }

tn3270eResMapSscpSuppliedName OBJECT-TYPE
    SYNTAX      SnaResourceName
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The name of the secondary LU (SLU) as it is known in the
         SNA network. This name is sent by the SSCP on the
         Activate Logical Unit (ACTLU) request. The value of this
         object is the empty string if the tn3270eResMapElementName
         is the same as the SSCP-supplied name."
 ::= { tn3270eResMapEntry 6 }

-- Define the set of objects to add to the Tcp Connection Table

tn3270eTcpConnTable OBJECT-TYPE
    SYNTAX SEQUENCE OF Tn3270eTcpConnEntry
    MAX-ACCESS not-accessible
    STATUS current
    DESCRIPTION

```

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

"Provides a table that has an entry for each TN3270(E)
client connection that is active at a TN3270E server.
The table was originally modeled after the tcpConnTable
but was changed to support different client Address types
and to be indexed first by the remote address and port
as oppose to local address and port. This is to enable
use of a SNMP GET-NEXT operation using only the remote
address and port."
 ::= { tn3270eObjects 9 }

tn3270eTcpConnEntry OBJECT-TYPE
SYNTAX Tn3270eTcpConnEntry
MAX-ACCESS not-accessible
STATUS current
DESCRIPTION
"Provides information about a single TN3270/TN3270E
session. Note: a tn3270eSrvrConfIndex is not needed
in this table since the combination of both remote
local addresses and ports is sufficient to
guarantee uniqueness between TN3270E Servers on the
same or actually different hosts."
INDEX { tn3270eTcpConnRemAddrType,
tn3270eTcpConnRemAddress,
tn3270eTcpConnRemPort,
tn3270eTcpConnLocalAddrType,
tn3270eTcpConnLocalAddress,
tn3270eTcpConnLocalPort
}
 ::= { tn3270eTcpConnTable 1 }

Tn3270eTcpConnEntry ::=
SEQUENCE
{
tn3270eTcpConnRemAddrType Tn3270eAddrType,
tn3270eTcpConnRemAddress Tn3270eTAddress,
tn3270eTcpConnRemPort Unsigned32,
tn3270eTcpConnLocalAddrType Tn3270eAddrType,
tn3270eTcpConnLocalAddress Tn3270eTAddress,
tn3270eTcpConnLocalPort Unsigned32,
tn3270eTcpConnLastActivity TimeTicks,
tn3270eTcpConnBytesIn Counter32,

tn3270eTcpConnBytesOut	Counter32,
tn3270eTcpConnResourceElement	SnaResourceName,
tn3270eTcpConnResourceType	Tn3270ResourceType,
tn3270eTcpConnDeviceType	Tn3270DeviceTypes,
tn3270eTcpConnFunctions	Tn3270Functions,
tn3270eTcpConnId	Unsigned32,
tn3270eTcpConnClientIdFormat	INTEGER,

Expires May 1998

[Page 31]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

tn3270eTcpConnClientId	OCTET STRING,
tn3270eTcpConnMiscInfoFormat	BITS,
tn3270eTcpConnMiscInfo	OCTET STRING,
tn3270eTcpConnLuLuBindImage	OCTET STRING,
tn3270eTcpConnSnaState	INTEGER

}

tn3270eTcpConnRemAddrType OBJECT-TYPE
SYNTAX Tn3270eAddrType
MAX-ACCESS not-accessible
STATUS current
DESCRIPTION
 "Indicates the type of the value of the
 tn3270eTcpConnRemAddress object. For example,
 ipv4(1) or ipv6(2)."
::= { tn3270eTcpConnEntry 1 }

tn3270eTcpConnRemAddress OBJECT-TYPE
SYNTAX Tn3270eTAddress
MAX-ACCESS not-accessible
STATUS current
DESCRIPTION
 "The remote address associated with a TN3270E client.
 tn3270eTcpConnRemAddrType indicates the address type
 (ipv4 or ipv6 for example).

If a TN3270(E) client is connected to its
server via a proxy client the address represented by
the value of this object should be the remote client's
address, not the proxy client's address."
::= { tn3270eTcpConnEntry 2 }

```
tn3270eTcpConnRemPort OBJECT-TYPE
    SYNTAX      Unsigned32 (0..65535)
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "The remote port associated with a TN3270E client.

        If a TN3270(E) client is connected to its
        server via a proxy client the port represented by
        the value of this object should be the remote client's
        port, not the proxy client's port."
::= { tn3270eTcpConnEntry 3 }
```

```
tn3270eTcpConnLocalAddrType OBJECT-TYPE
    SYNTAX     Tn3270eAddrType
    MAX-ACCESS not-accessible
```

Expires May 1998

[Page 32]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```
STATUS      current
DESCRIPTION
    "Indicates the type of the value of the
    tn3270eTcpConnLocalAddress object. For example,
    ipv4(1) or ipv6(2)."
::= { tn3270eTcpConnEntry 4 }
```

```
tn3270eTcpConnLocalAddress OBJECT-TYPE
    SYNTAX     Tn3270eTAddress
    MAX-ACCESS not-accessible
    STATUS      current
    DESCRIPTION
        "The local address associated with a TN3270E client.
        tn3270eTcpConnRemAddrType indicates the address type
        (ipv4 or ipv6 for example)."
::= { tn3270eTcpConnEntry 5 }
```

```
tn3270eTcpConnLocalPort OBJECT-TYPE
    SYNTAX      Unsigned32 (0..65535)
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "The remote port associated with a TN3270E client."
```

```

 ::= { tn3270eTcpConnEntry 6 }

tn3270eTcpConnLastActivity OBJECT-TYPE
    SYNTAX  TimeTicks
    MAX-ACCESS  read-only
    STATUS  current
    DESCRIPTION
        "The number of 100ths of seconds since any data was
         transferred for the associating TCP Connection."
    DEFVAL  { 0 }
 ::= { tn3270eTcpConnEntry 7 }

tn3270eTcpConnBytesIn  OBJECT-TYPE
    SYNTAX  Counter32
    UNITS "octets"
    MAX-ACCESS  read-only
    STATUS  current
    DESCRIPTION
        "The number of bytes received by the server from TCP
         for this connection."
 ::= { tn3270eTcpConnEntry 8 }

tn3270eTcpConnBytesOut  OBJECT-TYPE
    SYNTAX  Counter32
    UNITS "octets"

```

Expires May 1998

[Page 33]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
 1997

```

MAX-ACCESS  read-only
STATUS  current
DESCRIPTION
    "The number of bytes sent to TCP for this connection."
 ::= { tn3270eTcpConnEntry 9 }

tn3270eTcpConnResourceElement OBJECT-TYPE
    SYNTAX  SnaResourceName
    MAX-ACCESS  read-only
    STATUS  current
    DESCRIPTION
        "LU/Print secondary name for connecting an client
         into an SNA network."
 ::= { tn3270eTcpConnEntry 10 }

```

```

tn3270eTcpConnResourceType OBJECT-TYPE
    SYNTAX    Tn3270ResourceType
    MAX-ACCESS  read-only
    STATUS     current
    DESCRIPTION
        "Indicates the type of resource identified by
         tn3270eTcpConnResourceElement."
    ::= { tn3270eTcpConnEntry 11 }

tn3270eTcpConnDeviceType OBJECT-TYPE
    SYNTAX    Tn3270DeviceTypes
    MAX-ACCESS  read-only
    STATUS     current
    DESCRIPTION
        "Indicates the device type if negotiated with client.
         This object is also known as logmode."
    ::= { tn3270eTcpConnEntry 12 }

tn3270eTcpConnFunctions OBJECT-TYPE
    SYNTAX    Tn3270Functions
    MAX-ACCESS  read-only
    STATUS     current
    DESCRIPTION
        "This object will indicates which of the TN3270 and TN3270E
         functions that are supported by the server was negioted
         with a client. Refer to tn3270eSrvrFunctionsSupported."
    ::= { tn3270eTcpConnEntry 13 }

tn3270eTcpConnId OBJECT-TYPE
    SYNTAX      Unsigned32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION

```

Expires May 1998

[Page 34]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```

        "The connection identifier associated with a TN3270 or
         a TN3270E session's TCP connection."
    ::= { tn3270eTcpConnEntry 14 }

```

tn3270eTcpConnClientIdFormat OBJECT-TYPE

```

SYNTAX      INTEGER {
            unknown(0)
        }

MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
"The format of the corresponding tn3270eTcpConnClientId
object:

        ENUMERATION      OCTETS  DESCRIPTION
        unknown(0)          0"
::= { tn3270eTcpConnEntry 15 }

tn3270eTcpConnClientId OBJECT-TYPE
SYNTAX      OCTET STRING (SIZE (0..512))
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
"Additional client identification information whose
content is defined by the corresponding value of
tn3270eTcpConnClientIdFormat."
::= { tn3270eTcpConnEntry 16 }

tn3270eTcpConnMiscInfoFormat OBJECT-TYPE
SYNTAX      BITS {
            none(0),
            unknown(1),
            proxyIpv4(2),
            proxyIpv6(3)
        }
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
"This object defines the content of a corresponding
tn3270eTcpConnMiscInfo object. This object is defined
using the BITS SYNTAX in order to enable the presents
of multiple elements. The order of occurrence of the
selected elements in a tn3270eTcpConnMiscInfo must
follow the precedence of the associating BIT definition
with the exception of unknown(1) which must be last
if selected:

```

ENUMERATION	OCTETS	DESCRIPTION
none(0)	0	
unknown(1)	0..512	A variable length generic field.
proxyIpv4(2)	4	The actual client is connected via a proxy client whose address is stored in tn3270eTcpConnClientId.
proxyIpv6(3)	16	The actual client is connected via a proxy client whose address is stored in tn3270eTcpConnClientId.

For example, selection of unknown(1), proxyIpv4(2) and proxyIpv6(3) would result in the corresponding tn3270eTcpConnMiscInfo containing a proxyIpv6 value followed by a proxyIpv4 value and ended with a variable length unknown value."

::= { tn3270eTcpConnEntry 17 }

tn3270eTcpConnMiscInfo OBJECT-TYPE
SYNTAX OCTET STRING (SIZE (0..512))
MAX-ACCESS read-only
STATUS current
DESCRIPTION
"Additional client information. The contents of this object is defined by the corresponding object tn3270eTcpConnMiscInfoFormat."
 ::= { tn3270eTcpConnEntry 18 }

tn3270eTcpConnLuLuBindImage OBJECT-TYPE
SYNTAX OCTET STRING (SIZE (0..256))
MAX-ACCESS read-only
STATUS current
DESCRIPTION
"When there is a currently active LU-LU session for this connection, this object returns the BIND Image (defined to be bytes 1-p of the complete BIND Request Unit) that was received from the PLU during session activation. When there is no active LU-LU session, or when a BIND image is unavailable for some other reason, this object returns the empty string."
 ::= { tn3270eTcpConnEntry 19 }

tn3270eTcpConnSnaState OBJECT-TYPE
SYNTAX INTEGER {
 unknown(0),
 noSluSession(1),
 sscpLuSession(2), -- but no LU-LU session
 luLuSession(3)}

}

Expires May 1998

[Page 36]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"The current state of the SNA side of the end-to-end TN3270 connection. The following states are defined:

unknown(0) - The true state is not known.

noSluSession(1) - The SLU has neither an SSCP-LU nor an LU-LU session active.

sscpLuSession(2) - The SSCP-LU session for the SLU is active, but the SLU is not currently in session with a PLU.

luLuSession(3) - The SLU currently has an active session with a PLU."

::= { tn3270eTcpConnEntry 20 }

-- Conformance Definitions

tn3270eGroups OBJECT IDENTIFIER ::= { tn3270eConformance 1 }

tn3270eCompliances OBJECT IDENTIFIER ::= { tn3270eConformance 2 }

-- compliance statements

tn3270eCompliance MODULE-COMPLIANCE

STATUS current

DESCRIPTION

"The compliance statement for agents that support the TN3270E-MIB."

MODULE -- this module

MANDATORY-GROUPS { tn3270eBasicGroup,
 tn3270eSessionGroup
 }

GROUP tn3270eResMapGroup

DESCRIPTION

"This group is optional and provides a method of performing tn3270eClientGroup to tn3270eResPool mapping."

OBJECT tn3270eSrsvrConfActivityCheck

```

MIN-ACCESS  read-only
DESCRIPTION
    "The agent is not required to support a set to this
    object if the associating TN3270E server doesn't
    support either TIMEMARK or NOP processing. In
    this case an agent should return noCheck on
    retrieval."
OBJECT tn3270eSrvrConfActivityTimeout
    MIN-ACCESS  read-only
    DESCRIPTION

```

Expires May 1998

[Page 37]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```

    "The agent is not required to support a set to this
    object if the functions enabled by
    tn3270eSrvrConfActivityCheck are not supported.
    An agent in this case should return a value of 0."
OBJECT tn3270eSrvrConfActivityInterval
    MIN-ACCESS  read-only
    DESCRIPTION
        "The agent is not required to support a set to this
        object if the functions enabled by
        tn3270eSrvrConfActivityCheck are not supported.
        An agent in this case should return a value of 0."
OBJECT tn3270eSrvrConfAdminStatus
    DESCRIPTION
        "A TN3270E server is not required to support a
        stopImmediate state transition."
 ::= { tn3270eCompliances 1 }

-- units of conformance

tn3270eBasicGroup OBJECT-GROUP
    OBJECTS {
        tn3270eSrvrConfInactivityTimeout,
        tn3270eSrvrConfActivityCheck,
        tn3270eSrvrConfActivityTimeout,
        tn3270eSrvrConfActivityInterval,
        tn3270eSrvrFunctionsSupported,
        tn3270eSrvrConfAdminStatus,
        tn3270eSrvrConfOperStatus,
        tn3270eSrvrConfSessionTermState,

```

```
tn3270eSrvrConfSrvrType,
tn3270eSrvrConfContact,
tn3270eSrvrConfRowStatus,
tn3270eSrvrPortRowStatus,
tn3270eSrvrStatsUpTime,
tn3270eSrvrStatsMaxLus,
tn3270eSrvrStatsLusInUse,
tn3270eSrvrStatsSpareLus,
tn3270eSrvrStatsMaxPtrs,
tn3270eSrvrStatsPtrsInUse,
tn3270eSrvrStatsSparePtrs,
tn3270eSrvrStatsConnectsIn,
tn3270eSrvrStatsConnRejects,
tn3270eSrvrStatsDisconnects,
tn3270eSrvrStatsOctetsIn,
tn3270eSrvrStatsOctetsInLow,
tn3270eSrvrStatsOctetsOut,
tn3270eSrvrStatsOctetsOutLow,
tn3270eClientGroupSubnetMask,
```

Expires May 1998

[Page 38]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```
tn3270eClientGroupPfxLength,
tn3270eClientGroupRowStatus,
tn3270eSnaMapLocalName,
tn3270eSnaMapPrimaryLuName
}
STATUS current
DESCRIPTION
"This group is mandatory for all hosts supporting the
TN3270E-MIB."
::= { tn3270eGroups 1 }

tn3270eSessionGroup OBJECT-GROUP
OBJECTS {
    tn3270eResMapAddrType,
    tn3270eResMapAddress,
    tn3270eResMapPort,
    tn3270eResMapElementType,
    tn3270eResMapSscpSuppliedName,
    tn3270eTcpConnLastActivity,
    tn3270eTcpConnBytesIn,
```

```

tn3270eTcpConnBytesOut,
tn3270eTcpConnResourceElement,
tn3270eTcpConnResourceType,
tn3270eTcpConnDeviceType,
tn3270eTcpConnFunctions
}
STATUS current
DESCRIPTION
"This group is mandatory for all hosts supporting the
TN3270E-MIB."
 ::= { tn3270eGroups 2 }

tn3270eResMapGroup OBJECT-GROUP
OBJECTS {
tn3270eResPoolElementType,
tn3270eResPoolRowStatus,
tn3270eClientResMapRowStatus,
tn3270eTcpConnId,
tn3270eTcpConnClientIdFormat,
tn3270eTcpConnClientId,
tn3270eTcpConnMiscInfoFormat,
tn3270eTcpConnMiscInfo,
tn3270eTcpConnLuLuBindImage,
tn3270eTcpConnSnaState
}
STATUS current
DESCRIPTION
"This group is optional for all hosts supporting the

```

Expires May 1998

[Page 39]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

```

TN3270E-MIB."
 ::= { tn3270eGroups 3 }

```

END

5. Security Considerations

Certain management information defined in this MIB may be considered sensitive in some network environments. Therefore, authentication of

received SNMP requests and controlled access to management information should be employed in such environments. The method for this authentication is a function of the SNMP Administrative Framework, and has not been expanded by this MIB.

Several objects in this MIB allow write access or provide for remote creation. Allowing this support in a non-secure environment can have a negative effect on network operations. It is recommended that implementers seriously consider whether set operations should be allowed without providing, at a minimum, authentication of request origin. It is recommended that without such support that the following objects be implemented as read-only:

- o tn3270eSrvrConfInactivityTimout
- o tn3270eSrvrConfActivityCheck
- o tn3270eSrvrConfActivityTimeout
- o tn3270eSrvrConfActivityInterval
- o tn3270eSrvrConfAdminStatus
- o tn3270eSrvrConfSessionTermState
- o tn3270eSrvrConfContact
- o tn3270eClientGroupSubnetMask
- o tn3270eResPoolElementType

The following objects should either be implemented as read-only or not implemented when security is an issue as previously discussed:

- o tn3270eSrvrConfRowStatus
- o tn3270eSrvrPortRowStatus
- o tn3270eClientGroupRowStatus
- o tn3270eResPoolRowStatus
- o tn3270eResMapRowStatus

6. Acknowledgments

This document is a product of the TN3270E Working Group.

Expires May 1998

[Page 40]~

White TN3270E Management Information Base (TN3270E-MIB) 20 November
1997

7. References

- [1] SNMPv2 Working Group, Case, J., McCloghrie, K., Rose, M., and Waldbusser S., "Structure of Management Information for version 2 of the Simple Network Management Protocol (SNMPv2)", [RFC 1902](#), January 1996.
- [2] Network Working Group, Postel, J., and Reynolds, J., "Telnet Protocol Specification", [RFC 854](#), May 1983.
- [3] Network Working Group, Postel, J., and Reynolds, J., "Telnet Timing Mark Option", [RFC 860](#), May 1983.
- [4] Network Working Group and Rekhter J., "Telnet 3270 Regime Option", [RFC 1041](#), January 1988.
- [5] McCloghrie, K., and M. Rose, Editors, "Management Information Base for Network Management of TCP/IP-based internets: MIB-II", STD 17, [RFC 1213](#), Hughes LAN Systems, Performance Systems International, March 1991.
- [6] SNMPv2 Working Group, Case, J., McCloghrie, K., Rose, M., and S. Waldbusser, "Textual Conventions for version 2 of the Simple Network Management Protocol (SNMPv2)", [RFC 1903](#), January 1996.
- [7] SNMPv2 Working Group, Case, J., McCloghrie, K., Rose, M., and S. Waldbusser, "Protocol Operations for version 2 of the Simple Network Management Protocol (SNMPv2)", [RFC 1905](#), January 1996.
- [8] SNMPv2 Working Group, Case, J., McCloghrie, K., Rose, M., and S. Waldbusser, "Conformance Statements for version 2 of the Simple Network Management Protocol (SNMPv2)", [RFC 1904](#), January 1996.
- [9] Case, J., M. Fedor, M. Schoffstall, J. Davin, "Simple Network Management Protocol", [RFC 1157](#), SNMP Research, Performance Systems International, MIT Laboratory for Computer Science, May 1990.
- [10] IETF SNMPv2 Working Group and McCloghrie, K., "TCP-MIB

Definitions", November 1994.

- [11] Hinden, R., Deering, S., "IP Version 6 Addressing Architecture",
<draft-ietf-ipngwg-addr-arch-v2-02.txt>, July 16, 1997
- [12] Krupczak, Cheryl, Saperia, Jonathan, "Definitions of System-Level
Managed Objects for Applications", April 15, 1997.

8. Authors' Address

Kenneth D. White
Dept. G80/Bldg 501
IBM Corporation
Research Triangle Park, NC 27709, USA
E-mail: kennethw@vnet.ibm.com

Expires May 1998

[Page 42]~