# Yang data model for Terminal Access Controller Access Control System Plus

draft-zheng-opsawg-tacacs-yang

Guangying Zheng
Zitao Wang
Bo Wu
Huawei Technologies


### Why this draft is needed?

#### Motivations

- ietf-system.yang [RFC 7317] only covers Radius as the centralized authentication mechanism.
- This draft defines TACACS+ client YANG model based on the TACACS+ Protocol draft to augment the system YANG.
  - TACACS+ authentication method which is widely used;
  - the authorization and accounting properties is missing.
- Having a standardized model makes life much easier for operators

#### Draft background

- Initially proposed in Netmod
- Model re-structure based on comments received from Netmod list.




#### Tacacs+ client model Overview

Augments RFC 7317 (system management)

The data model for configuration of the TACACS+ client has the

following structure:



## Solicit help from WG

 Please read and comment whether this model can cover your Implementation requirement of Tacacs+ client Netconf configuration.

## Backup slides

# Current Structure (system augmentation)

odule: ietf-tacacs					
augment /sys:system:					
+rw tacacs {tacacs}?					
+rw enable?	boolean				
+rw tacacs-servers					
+rw timeout?	uint32			+ro author-reqs-num?	uint32
+rw quiet-time? uint32				+ro author-rsps-num?	uint32
+rw shared-key? password-extend		d		+ro author-errors?	uint32
+rw source-ip? inet:ip-address				+ro author-errors?	umt52
+rw tacacs-server* [	name]			+ro acct-reqs-num?	uint32
+rw name		string		+ro acct-rsps-num? +ro acct-srv-connected-num?	
+rw server-ip?		inet:ip-address			
+rw server-type?		server-type			
+rw network-instance?		-> /ni:network-instances	•	+ro acct-srv-disconnected-num?	uint32
		/network-instance/name		+ro account-rsp-err?	uint32
+rw server-port?		uint32		To account-15p-ci1.	
+rw single-connection?		boolean			
+ro server-state?		server-state	rpcs:	rpcs: +x rest-all-statistics +x reset-authen-statistics +x reset-author-statistics +x reset-account-statistics +x reset-common-statistics	
+ro current-srv?		boolean			
+rw shared-key?		password-extend	+X I		
+ro authen-srv-connected-num?		uint32	+ <b>x</b> 1		
+ro authen-srv-disconnected-num?		uint32	+ <b>x</b> 1		
+ro authen-reqs-num?		uint32			
+ro authen-rsps-num?		uint32	+x 1		
+ro authen-errors?		uint32	+x 1		
+ro author-srv-connected-num?		uint32			
+ro author-srv-disconnected-num?		uint32			6