NTP

Internet-Draft

Expires: January 10, 2008

H. Gerstung
Meinberg
C. Elliott
Cisco
July 9, 2007

Definitions of Managed Objects for Network Time Protocol Version 4 (NTPv4) draft-ietf-ntp-ntpv4-mib-02

Status of this Memo

By submitting this Internet-Draft, each author represents that any applicable patent or other IPR claims of which he or she is aware have been or will be disclosed, and any of which he or she becomes aware will be disclosed, in accordance with <u>Section 6 of BCP 79</u>.

Internet-Drafts are working documents of the Internet Engineering Task Force (IETF), its areas, and its working groups. Note that other groups may also distribute working documents as Internet-Drafts.

Internet-Drafts are draft documents valid for a maximum of six months and may be updated, replaced, or obsoleted by other documents at any time. It is inappropriate to use Internet-Drafts as reference material or to cite them other than as "work in progress."

The list of current Internet-Drafts can be accessed at http://www.ietf.org/ietf/lid-abstracts.txt.

The list of Internet-Draft Shadow Directories can be accessed at http://www.ietf.org/shadow.html.

This Internet-Draft will expire on January 10, 2008.

Copyright Notice

Copyright (C) The IETF Trust (2007).

Abstract

The Network Time Protocol (NTP) is used in networks of all types and sizes for time synchronization of servers, workstations and other networked equipment. As time synchronization is more and more a mission critical service, standardized means for monitoring and management of this subsystem of a networked host are required to allow operators of such a service to setup a monitoring system that

is platform- and vendor-independant. This RFC draft provides a standardized collection of data objects for monitoring the NTP service of such a network participant and it is part of the NTP Version 4 standardization effort.

Table of Contents

<u>1</u> .	The Internet-Standard Management Framework	<u>3</u>		
<u>2</u> .	Introduction	<u>3</u>		
<u>3</u> .	Technical Description	<u>3</u>		
<u>4</u> .	MIB Definition	<u>4</u>		
<u>5</u> .	IANA Considerations	<u>0</u>		
<u>6</u> .	Security Considerations	0		
<u>7</u> .	References	<u>0</u>		
7.	$\underline{.1}$. Normative References	<u>0</u>		
7.	$\underline{\tt .2}$. Informative References	<u>0</u>		
Auth	hors' Addresses	1		
Intellectual Property and Copyright Statements				

1. The Internet-Standard Management Framework

For a detailed overview of the documents that describe the current Internet-Standard Management Framework, please refer to section 7 of RFC3410 [4].

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. MIB objects are generally accessed through the Simple Network Management Protocol (SNMP). Objects in the MIB are defined using the mechanisms defined in the Structure of Management Information (SMI). This memo specifies a MIB module that is compliant to the SMIv2, which is described in RFC2578 [1], RFC2579 [2] and RFC2580 [3].

2. Introduction

The NTPv4 MIB Module is designed to allow SNMP to be used to monitor and manage local NTP service instances. It provides a collection of data objects that can be gueried using the SNMP protocol and represent the current status of the NTP service instance. This includes general information about the NTP service instance itself (vendor, product, version) as well as connectivity to upstream NTP servers used as sources of reference time and to hardware reference clocks like radio clocks. The most important values are included in order to be able to detect failures before they can have an impact on the overall time synchronization status of the network. There are also a collection of notification objects to inform about state changes in the NTP service. There are objects to control these notifications as well.

3. Technical Description

The NTPv4 MIB Module is divided into sections for general server information, current NTP service status, status information of all mobilized associations (e.g. unicast upstream time servers, multicast or broadcast time references and hardware clocks), NTP service control objects, NTP objects used only for notifications, as well as SNMP notification definitions for core events.

The general server information section contains static information and can be queried to identify which NTP service implementation is running on a host. This includes the vendor and product name of the running NTP software as well as version information, hardware/os platform identity and the time resolution of the underlying OS.

Section 2 (current NTP status) includes data objects that represent

the current operational status of the NTP service instance.

The third section contains data objects that represent the set of time references ("associations") the NTP instance is currently working with.

The fourth section contains objects that can be used to control the NTP service. The currently defined objects control how often the heartbeat interval notification is sent out and which notifications are enabled.

The fifth section contains objects that are only used as varbinds in notifications. There is currently only one object in this section -- a message that adds a clear text event message to notifications.

Certain important events can occur while the NTP instance is running. The sixth section defines SNMP notifications for a collection of the most important ones ("core events") and additionally provides a heartbeat notification as well as a test notification to allow management systems to test the reception of NTP related notifications as well as enable heartbeat-based monitoring systems to assure that the NTP service is still up and running.

4. MIB Definition

```
--$Id: draft-ietf-ntp-ntpv4-mib-00.xml 1.7 2006/06/16 07:13:50Z heiko TRASH $
-- $Name: SUBMIT 1 $
     The Network Time Protocol Version 4
     Management Information Base (MIB)
     Authors: Heiko Gerstung (heiko.gerstung@meinberg.de)
             Chris Elliott (chelliot@cisco.com)
     for the Internet Engineering Task Force (IETF)
     NTP Working Group (ntpwg)
- -
  ********************
  $Log: draft-ietf-ntp-ntpv4-mib-00.xml $
  -- Revision 1.10 2007/07/09 00:00:00Z chelliot
     MIB:
       - Changed "service" and "service instance" to "entity",
       - and Srv to Ent
```

- -- Changed RFC to Internet
- -- Changed status to mode
- -- Added association status object
- -- Added leap second objects
- -- Revision 1.9 2007/03/04 06:59:44Z chelliot
- -- MIB:
- -- Added time objects, comments, changed notifications
- -- Changed server to service
- -- Revision 1.8 2006/10/23 03:37:44Z chelliot
- -- MIB:
- -- Changed various object types, added notification control object
- -- Revision 1.7 2006/06/16 07:13:50Z heiko
- -- XML/RFC:
- -- added/changed comments about the to-be-done IANA SMI assignment
- -- Revision 1.6 2006/06/16 07:04:43Z heiko
- -- RFC/XML:
- -- phone number corrected
- -- removed unused references
- -- MIB:
- -- added ntpSrvTimePrecision
- -- changed INTEGER objects to Integer32
- -- changed default value for ntpSrvStatusStratum from 99 to 16
- -- changed default value for ntpSrvStatusActiveRefclockId from 99 to 0
- -- changed object names to ntpSrvStatusActiveRefSourceName
- -- (from ntpSrvStatusActiveRefclockName) and to
- -- ntpSrvStatusNumberOfRefSources (from ntpSrvStatusNumberOfRefclocks)
- -- removed ntpSrvStatusAuthKeyId object
- -- added ntpSrvStatusDispersion to provide the current root dispersion
- -- major rework of <u>section 3</u> (Status of associations) to compile cleanly including:
- -- added dispersion to the association dataset
- -- renaming of objects
- -- added an index to the association table
- -- formal changes
- -- traps are now reverse mappable
- -- traps are now define with payload where applicable
- -- added compliance statements
- -- Revision 1.5 2006/02/27 08:28:16Z heiko
- -- changed to RFC format and added header as well as
- -- introduction and technical description
- -- added other necessary RFC components (copyright statement etc.)
- -- Revision 1.4 2006/02/27 07:06:49Z heiko
- -- removed all objects with data type REAL
- -- everything that needs to be floating point is now defined as
- -- DisplayString
- -- Revision 1.2 2006/01/23 08:58:11Z heiko
- -- changed the datatype of offset, jitter and delay objects from Integer32
- -- to REAL

```
NTPv4-MIB DEFINITIONS ::= BEGIN
IMPORTS
   MODULE-IDENTITY, OBJECT-TYPE, mib-2, Integer32, NOTIFICATION-TYPE,
   Unsigned32
       FROM SNMPv2-SMI
   MODULE-COMPLIANCE, OBJECT-GROUP, NOTIFICATION-GROUP
       FROM SNMPv2-CONF
   DisplayString
       FROM SNMPv2-TC
   InetAddressType, InetAddress
       FROM INET-ADDRESS-MIB;
ntpSnmpMIB MODULE-IDENTITY
   LAST-UPDATED "200707090000Z" -- July 9, 2007
   ORGANIZATION "The IETF NTP Working Group (ntpwg)"
   CONTACT-INFO
                WG Email:
                Subscribe:
                Editor 1 name
                Title
                Employeer
                Address
                Phone
                email
                Editor 2 name..."
   DESCRIPTION
       "The Management Information Base for NTP time entities."
   REVISION
               "200707090000Z"
   DESCRIPTION
       "Multiple changes from IETF 68"
               "200703040000Z"
   REVISION
   DESCRIPTION
       "More MIB review modifications."
   REVISION
              "200610230000Z"
   DESCRIPTION
       "Modifications from MIB review."
               "200606190000Z"
   REVISION
   DESCRIPTION
       "First Draft Version"
               "200512190000Z"
   REVISION
   DESCRIPTION
```

```
"revised edition (added traps and stuff)"
                 "200511160000Z"
    REVISION
    DESCRIPTION
        "Initial draft"
    ::= { mib-2 99999 }
ntpSnmpMIBObjects OBJECT IDENTIFIER ::= { ntpSnmpMIB 1 }
-- MIB contains 4 groups
ntpEntInfo
                   OBJECT IDENTIFIER ::= { ntpSnmpMIBObjects 1 }
                   OBJECT IDENTIFIER ::= { ntpSnmpMIBObjects 2 }
ntpEntStatus
ntpAssociation
ntpEntControl
                   OBJECT IDENTIFIER ::= { ntpSnmpMIBObjects 3 }
                   OBJECT IDENTIFIER ::= { ntpSnmpMIBObjects 4 }
ntpEntNotifObjects OBJECT IDENTIFIER ::= { ntpSnmpMIBObjects 5 }
ntpEntNotifPrefix OBJECT IDENTIFIER ::= { ntpSnmpMIBObjects 6 }
-- <u>Section 1</u>: General NTP Entity information objects
              (relatively static information)
ntpEntSoftwareName OBJECT-TYPE
    SYNTAX
             DisplayString
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "The product name of the installed NTP version."
    -- the product name of the running ntp implementation, e.g. "ntpd"
    ::= { ntpEntInfo 1 }
ntpEntSoftwareVersion OBJECT-TYPE
    SYNTAX
                DisplayString
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "The software version of the installed NTP implementation."
    -- full version string, e.g. "ntpd-4.2.0b@1.1433 ..."
    ::= { ntpEntInfo 2 }
ntpEntSoftwareVersionVal OBJECT-TYPE
                Unsigned32
    SYNTAX
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "Software version of installed NTP as an unsigned integer value."
    -- e.g. if version string is "4.2.0b" this could be translated into 4202
```

```
-- could be useful to find out if version of entity on a is newer or older
    -- than version of the entity on b (without too much string parsing
trouble)
    ::= { ntpEntInfo 3 }
ntpEntSoftwareVendor OBJECT-TYPE
   SYNTAX DisplayString
   MAX-ACCESS read-only
   STATUS
               current
    DESCRIPTION
       "The vendor/author of the installed NTP version."
    ::= { ntpEntInfo 4 }
ntpEntSystemType OBJECT-TYPE
    SYNTAX
           DisplayString
   MAX-ACCESS read-only
   STATUS
               current
    DESCRIPTION
       "General hardware/os platform information."
    -- e.g. "Linux 2.6.12 / x86"
    -- freely configurable, default is OS Version / Hardware platform
    ::= { ntpEntInfo 5 }
ntpEntTimeResolution OBJECT-TYPE
    SYNTAX
               DisplayString
   MAX-ACCESS read-only
               current
   STATUS
    DESCRIPTION
        "A string describing the time resolution of the running NTP
        implementation."
    -- e.g. "100 ns"
    -- depends on the NTP implementation and the underlying OS. The current
    -- resolution should be used, so if the OS only supports 10ms and ntpd is
    -- capable of 1ns, the 10ms should be advertised
    ::= { ntpEntInfo 6 }
ntpEntTimeResolutionVal OBJECT-TYPE
    SYNTAX Unsigned32
    MAX-ACCESS read-only
   STATUS
               current
    DESCRIPTION
       "The time resolution in integer format."
    -- ntpEntTimeResolution in Integer format
    -- shows the resolution based on 1 second, e.g. "1ms" translates to 1000
    ::= { ntpEntInfo 7 }
ntpEntTimePrecision OBJECT-TYPE
    SYNTAX
               DisplayString
```

Gerstung & Elliott Expires January 10, 2008 [Page 8]

```
STATUS
                current
    DESCRIPTION
        "A string describing the precision with which the NTP entity
         implementation/OS manages its time base."
    -- e.g. "-18" means 2^{-18} = 0.000003814697265625 seconds
            "-5" means 2^{-5} = 0.03125 seconds
    -- depends on the NTP implementation and the underlying OS.
    ::= { ntpEntInfo 8 }
ntpEntTimePrecisionVal OBJECT-TYPE
    SYNTAX
                Integer32
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "The entity's precision in integer format."
    -- ntpEntTimePrecision in signed Integer format
    -- shows the precision. A value of -5 would mean 2^-5 = 31.25 ms
    ::= { ntpEntInfo 9 }
ntpEntTimeDistance OBJECT-TYPE
    SYNTAX
                DisplayString
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "The distance from this NTP instance to the root time reference
       (stratum 0) source."
    -- including the unit
    -- e.g. "13.243 ms"
    ::= { ntpEntInfo 10 }
-- <u>Section 2</u>: Current NTP status (dynamic information)
ntpEntStatusCurrentMode OBJECT-TYPE
    SYNTAX
              DisplayString
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "The actual mode of NTP as a string"
    --- possible strings:
    --- "not running" : NTP is not running
    --- "not synchronized" : NTP is not synchronized to any time source
          (stratum = 16)
    --- "none configured" : NTP is not synchronized and does not have a server
                            configured
        (stratum = 16)
    --- "sync to local" : NTP is synchronized to own local clock
```

```
(degraded reliability)
    --- "sync to refclock" : NTP is synchronized to a local hardware refclock
          (e.g. GPS)
    --- "sync to remote server" : NTP is synchronized to a remote NTP server
         ("upstream" server)
    --- "unknown" : The state of NTP is unknown.
    ::= { ntpEntStatus 1 }
ntpEntStatusCurrentModeVal OBJECT-TYPE
    SYNTAX
                INTEGER {
                            notRunning(1),
                            notSynchronized(2),
                            noneConfigured(3),
                            syncToLocal(4),
                            syncToRefclock(5),
                            syncToRemoteServer(6),
                            unknown(99)
                        }
    MAX-ACCESS read-only
    STATUS
               current
    DESCRIPTION
        "The current mode of the NTP as integer value."
    -- see ntpEntStatusCurrentMode
    DEFVAL { 99 }
    ::= { ntpEntStatus 2 }
ntpEntStatusStratum OBJECT-TYPE
    SYNTAX Unsigned32 (1..16)
    MAX-ACCESS read-only
    STATUS
               current
    DESCRIPTION
        "The NTP entity's own stratum value."
    -- should be stratum of syspeer + 1 (or 16 if no syspeer)
    DEFVAL { 16 }
    ::= { ntpEntStatus 3 }
ntpEntStatusActiveRefSourceId OBJECT-TYPE
    SYNTAX Unsigned32 ( 0..99999 )
   MAX-ACCESS read-only
               current
    STATUS
    DESCRIPTION
       "The association ID of the current syspeer."
    DEFVAL { 0 }
    ::= { ntpEntStatus 4 }
ntpEntStatusActiveRefSourceName OBJECT-TYPE
    SYNTAX
               DisplayString
    MAX-ACCESS read-only
```

```
STATUS
                current
    DESCRIPTION
        "The hostname/descriptive name of the current reference source
         selected as syspeer."
    -- e.g. "ntp1.ptb.de" or "GPS" or "DCFi" ...
    -- maybe something like "RefClk(8)" = "hardware clock using driver 8"
    -- would be nice
    ::= { ntpEntStatus 5 }
ntpEntStatusActiveOffset OBJECT-TYPE
    SYNTAX
                DisplayString
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "The Time offset to the current selected reference time source as
         a string."
    -- including unit, e.g. "0.032 ms" or "1.232 s"
    ::= { ntpEntStatus 6 }
ntpEntStatusNumberOfRefSources OBJECT-TYPE
    SYNTAX
                Unsigned32 (0..99)
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "The number of reference sources configured for NTP."
    DEFVAL { 0 }
    ::= { ntpEntStatus 7 }
ntpEntStatusDispersion OBJECT-TYPE
    SYNTAX
                DisplayString
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "The root dispersion of the running NTP instance."
    -- e.g. "6.927"
    DEFVAL { "n/a" }
    ::= { ntpEntStatus 8 }
ntpEntStatusEntityUptime OBJECT-TYPE
    SYNTAX
                Unsigned32
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "The uptime of the NTP entity in seconds."
    -- time since ntpd was (re-)started (not sysUptime!)
    DEFVAL { 0 }
    ::= { ntpEntStatus 9 }
```

```
ntpEntStatusTime OBJECT-TYPE
    SYNTAX
                OCTET STRING (SIZE (0 | 16))
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "The current NTP time on the device, in 128-bit
         NTP date format. Ref: draft-ietf-ntp-ntpv4-proto-04,
         section 5:
          It includes a 64-bit signed seconds field
          spanning 584 billion years and a 64-bit fraction
          field resolving .05 attosecond (i.e. 0.5e-18).
          For convenience in mapping between formats, the
          seconds field is divided into a 32-bit era field
          and a 32-bit timestamp field.
         If time is not syncronized this field shall be a
         zero-length string.
         This object can be used to timestamp events on this
         node and allow a management station to coorelate
         different time objects. For example, a management
         station could query this object and sysUpTime in
         the same operation to be able to relate sysUpTime
         to NTP time.
         This object is not to be used to set the time of
         the node querying this object. NTP should be used
         for this--or at least SNTP."
    ::= { ntpEntStatus 10 }
ntpEntStatusLeapSecond OBJECT-TYPE
                Integer32
    SYNTAX
    MAX-ACCESS read-only
                current
    STATUS
    DESCRIPTION
        "Date the next known leap second will occur"
    DEFVAL { 0 }
    ::= { ntpEntStatus 11 }
ntpEntStatusLeapSecDirection OBJECT-TYPE
                Integer32 (-1..1)
    SYNTAX
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "Direction of next known leap second"
    DEFVAL { 0 }
    ::= { ntpEntStatus 12 }
```

```
-- <u>Section 3</u>: The status of all currently mobilized associations
ntpAssociationTable OBJECT-TYPE
    SYNTAX
                     SEQUENCE OF NtpAssociationEntry
   MAX-ACCESS
                     not-accessible
    STATUS
                     current
    DESCRIPTION
        "The table of currently mobilized associations."
    ::= { ntpAssociation 1 }
ntpAssociationEntry OBJECT-TYPE
    SYNTAX
             NtpAssociationEntry
   MAX-ACCESS not-accessible
    STATUS
               current
    DESCRIPTION
        "The table entry of currently mobilized associations."
    INDEX
                { ntpAssocId }
    ::= { ntpAssociationTable 1 }
NtpAssociationEntry ::= SEQUENCE {
        ntpAssocId
                                    Unsigned32,
        ntpAssocName
                                    DisplayString,
        ntpAssocRefId
                                    DisplayString,
        ntpAssocAddressType
                                    InetAddressType,
                                    InetAddress,
        ntpAssocAddress
        ntpAssocOffset
                                    DisplayString,
        ntpAssocStratum
                                    Integer32,
        ntpAssocStatusJitter
                                    DisplayString,
                                    DisplayString,
        ntpAssocStatusDelay
        ntpAssocStatusDispersion
                                    DisplayString
}
ntpAssocId
                OBJECT-TYPE
    SYNTAX
                Unsigned32 ( 1..99999 )
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
        "The association ID. This is an internal, unique ID."
    ::= { ntpAssociationEntry 1 }
                OBJECT-TYPE
ntpAssocName
    SYNTAX
                DisplayString
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "The hostname or other descriptive name for the association."
```

```
::= { ntpAssociationEntry 2 }
               OBJECT-TYPE
ntpAssocRefId
    SYNTAX
               DisplayString
   MAX-ACCESS read-only
   STATUS
               current
   DESCRIPTION
       "The refclock driver ID, if available."
    -- a refclock driver ID like "127.127.1.0" for non uni/multi/broadcast
    -- associations
    ::= { ntpAssociationEntry 3 }
ntpAssocAddressType OBJECT-TYPE
    SYNTAX
               InetAddressType
   MAX-ACCESS read-only
   STATUS
               current
   DESCRIPTION
        "The type of address of the association."
    -- contains the type of address for uni/multi/broadcast associations
    ::= { ntpAssociationEntry 4 }
ntpAssocAddress OBJECT-TYPE
   SYNTAX InetAddress
   MAX-ACCESS read-only
   STATUS
               current
    DESCRIPTION
       "The IP address (IPv4 or IPv6) of the association."
    -- contains IP address of uni/multi/broadcast associations
    ::= { ntpAssociationEntry 5 }
ntpAssocOffset OBJECT-TYPE
   SYNTAX
               DisplayString
   MAX-ACCESS read-only
               current
   STATUS
   DESCRIPTION
       "The time offset to the association as a string."
    -- including unit, e.g. "0.032 ms" or "1.232 s"
    ::= { ntpAssociationEntry 6 }
ntpAssocStratum OBJECT-TYPE
               Integer32 (1..16)
    SYNTAX
   MAX-ACCESS read-only
   STATUS
               current
    DESCRIPTION
        "The association stratum value."
    ::= { ntpAssociationEntry 7 }
ntpAssocStatusJitter OBJECT-TYPE
```

```
SYNTAX
               DisplayString
   MAX-ACCESS read-only
    STATUS
           current
    DESCRIPTION
        "The jitter in miliseconds as a string."
    ::= { ntpAssociationEntry 8 }
ntpAssocStatusDelay OBJECT-TYPE
    SYNTAX
            DisplayString
   MAX-ACCESS read-only
               current
    STATUS
    DESCRIPTION
        "The network delay in miliseconds as a string."
    ::= { ntpAssociationEntry 9 }
ntpAssocStatusDispersion OBJECT-TYPE
    SYNTAX
               DisplayString
   MAX-ACCESS read-only
    STATUS
               current
    DESCRIPTION
        "The root dispersion of the association."
    -- e.g. "6.927"
    ::= { ntpAssociationEntry 10 }
-- <u>Section 4</u>: Control objects
ntpEntHeartbeatInterval OBJECT-TYPE
    SYNTAX
           Unsigned32
   MAX-ACCESS read-write
               current
    STATUS
    DESCRIPTION
        "The interval at which the ntpEntNotifHeartbeat notification should be
         sent, in seconds. If set to 0 and the srvNotifHeartbeat bit in
         ntpEntNotifBits is 1 then ntpEntNotifHeartbeat is sent once."
    DEFVAL { 60 }
    ::= { ntpEntControl 1 }
ntpEntNotifBits OBJECT-TYPE
    SYNTAX
                 BITS {
                     notUsed(0), -- Used to sync up bit and notification
                                 -- indices
                     srvNotifNotSync(1),
                     srvNotifEntityStarted(2),
                     srvNotifEntityStopped(3),
                     srvNotifStratumChange(4),
                     srvNotifSyspeerChanged(5),
```

```
srvNotifAddAssociation(6),
                     srvNotifRemoveAssociation(7),
                     srvNotifConfigChanged(8),
                     srvNotifLeapSecondAnnounced(9),
                     srvNotifHeartbeat(10)
    }
    MAX-ACCESS read-write
    STATUS
                current
    DESCRIPTION
        "A bit for each notification. A 1 for a particular bit enables
         that particular notification, a 0 disables it."
    ::= { ntpEntControl 2 }
-- Section 5: Notification objects
ntpEntNotifMessage OBJECT-TYPE
    SYNTAX
                DisplayString
   MAX-ACCESS accessible-for-notify
    STATUS
               current
    DESCRIPTION
        "Used as a payload object for all notifications. Holds a clear text
         event message."
    DEFVAL { "no event" }
    ::= { ntpEntNotifObjects 1 }
-- SNMP notification definitions
ntpEntNotifications OBJECT IDENTIFIER ::= { ntpEntNotifPrefix 0 }
ntpEntNotifNotInSync NOTIFICATION-TYPE
    OBJECTS
                { ntpEntStatusCurrentModeVal }
    STATUS
                current
    DESCRIPTION
        "The notification to be sent when the NTP entity transistions to
         not synchronised."
    ::= { ntpEntNotifications 1 }
ntpEntNotifEntityStarted NOTIFICATION-TYPE
                { ntpEntNotifMessage }
    OBJECTS
                current
    STATUS
    DESCRIPTION
        "The notification to be sent when NTP starts up."
    ::= { ntpEntNotifications 2 }
```

```
ntpEntNotifEntityStopped NOTIFICATION-TYPE
    OBJECTS 
                { ntpEntNotifMessage }
    STATUS
                current
    DESCRIPTION
        "The notification to be sent when NTP stops."
    ::= { ntpEntNotifications 3 }
ntpEntNotifStratumChange NOTIFICATION-TYPE
    OBJECTS
                { ntpEntStatusTime, ntpEntStatusStratum,
                  ntpEntNotifMessage }
    STATUS
                current
    DESCRIPTION
        "The notification to be sent when stratum level of NTP changes."
    ::= { ntpEntNotifications 4 }
ntpEntNotifSyspeerChanged NOTIFICATION-TYPE
    OBJECTS
                { ntpEntStatusTime, ntpEntStatusActiveRefSourceId,
                  ntpEntNotifMessage }
    STATUS
                current
    DESCRIPTION
        "The notification to be sent when a (new) syspeer has been selected."
    ::= { ntpEntNotifications 5 }
ntpEntNotifAddAssociation NOTIFICATION-TYPE
                { ntpEntStatusTime, ntpAssocName, ntpEntNotifMessage }
    OBJECTS
    STATUS
                current
    DESCRIPTION
        "The notification to be sent when a new association is mobilized."
    ::= { ntpEntNotifications 6 }
ntpEntNotifRemoveAssociation NOTIFICATION-TYPE
                { ntpEntStatusTime, ntpAssocName, ntpEntNotifMessage }
    OBJECTS
    STATUS
                current
    DESCRIPTION
        "The notification to be sent when an association is demobilized."
    ::= { ntpEntNotifications 7 }
ntpEntNotifConfigChanged NOTIFICATION-TYPE
                { ntpEntStatusTime, ntpEntNotifMessage }
    OBJECTS
    STATUS
                current
    DESCRIPTION
        "The notification to be sent when the NTP configuration has changed."
    -- e.g. when the system connected to the internet and was assigned
    -- a new IP address by the ISPs DHCP server
    ::= { ntpEntNotifications 8 }
ntpEntNotifLeapSecondAnnounced NOTIFICATION-TYPE
    OBJECTS
                { ntpEntStatusTime, ntpEntNotifMessage }
```

```
STATUS
                current
    DESCRIPTION
        "The notification to be sent when a leap second has been announced."
    ::= { ntpEntNotifications 9 }
ntpEntNotifHeartbeat NOTIFICATION-TYPE
                { ntpEntStatusTime, ntpEntStatusCurrentModeVal,
                  ntpEntHeartbeatInterval, ntpEntNotifMessage }
    STATUS
                current
    DESCRIPTION
        "The notification to be sent periodically (as defined by
         ntpEntHeartbeatInterval) to indicate that the NTP entity is still
         alive."
    ::= { ntpEntNotifications 10 }
-- Conformance/Compliance statements
ntpEntConformance OBJECT IDENTIFIER ::= { ntpSnmpMIB 6 }
ntpEntCompliances OBJECT IDENTIFIER ::= { ntpEntConformance 1 }
ntpEntGroups
                  OBJECT IDENTIFIER ::= { ntpEntConformance 2 }
ntpEntCompliance MODULE-COMPLIANCE
    STATUS
                current
    DESCRIPTION
        "The compliance statement for SNMP entities which implement the NTP
         MIB"
    MODULE -- this module
        MANDATORY-GROUPS {
                           ntpEntObjectsGroup,
                           ntpEntNotifPrefixGroup
        }
        ::= { ntpEntCompliances 1 }
ntpEntObjectsGroup OBJECT-GROUP
    OBJECTS {
              ntpEntSoftwareName,
              ntpEntSoftwareVersion,
              ntpEntSoftwareVersionVal,
              ntpEntSoftwareVendor,
              ntpEntSystemType,
              ntpEntTimeResolution,
              ntpEntTimeResolutionVal,
              ntpEntTimePrecision,
              ntpEntTimePrecisionVal,
              ntpEntTimeDistance,
```

```
ntpEntStatusCurrentMode,
              ntpEntStatusCurrentModeVal,
              ntpEntStatusStratum,
              ntpEntStatusActiveRefSourceId,
              ntpEntStatusActiveRefSourceName,
              ntpEntStatusActiveOffset,
              ntpEntStatusNumberOfRefSources,
              ntpEntStatusDispersion,
              ntpEntStatusEntityUptime,
              ntpEntStatusTime,
              ntpEntStatusLeapSecond,
              ntpEntStatusLeapSecDirection,
              ntpAssocName,
              ntpAssocRefId,
              ntpAssocAddressType,
              ntpAssocAddress,
              ntpAssocOffset,
              ntpAssocStratum,
              ntpAssocStatusJitter,
              ntpAssocStatusDelay,
              ntpAssocStatusDispersion,
              ntpEntHeartbeatInterval,
              ntpEntNotifBits,
              ntpEntNotifMessage
    }
    STATUS
                current
    DESCRIPTION
        "The collection of objects for the NTP MIB"
    ::= { ntpEntGroups 1 }
ntpEntNotifPrefixGroup NOTIFICATION-GROUP
    NOTIFICATIONS {
                    ntpEntNotifNotInSync,
                    ntpEntNotifEntityStarted,
                    ntpEntNotifEntityStopped,
                    ntpEntNotifStratumChange,
                    ntpEntNotifSyspeerChanged,
                    ntpEntNotifAddAssociation,
                    ntpEntNotifRemoveAssociation,
                    ntpEntNotifConfigChanged,
                    ntpEntNotifLeapSecondAnnounced,
                    ntpEntNotifHeartbeat
    STATUS
                current
    DESCRIPTION
        "The collection of notifications for the NTP MIB"
    ::= { ntpEntGroups 2 }
```

END

5. IANA Considerations

The MIB module in this document uses the following IANA-assigned OBJECT IDENTIFIER values recorded in the SMI Numbers registry:

Descriptor	OBJECT IDENTIFIER value
ntpSnmp	{ mib-2 XXX }

RFC Ed.: the IANA is requested to assign a value for "XXX" under the 'mib-2' subtree and to record the assignment in the SMI Numbers registry. When the assignment has been made, the RFC Editor is asked to replace "XXX" (here and in the MIB module) with the assigned value and to remove this note.

Security Considerations

All data objects in this MIB are read-only and therefore security is managed by the implementation of the SNMP agent providing the data objects in this MIB. The general access management methods used for SNMP agents apply.

7. References

7.1. Normative References

- [1] McCloghrie, K., Ed., Perkins, D., Ed., and J. Schoenwaelder, Ed., "Structure of Management Information Version 2 (SMIv2)", STD 58, RFC 2578, April 1999.
- [2] McCloghrie, K., Ed., Perkins, D., Ed., and J. Schoenwaelder, Ed., "Textual Conventions for SMIv2", STD 58, RFC 2579, April 1999.
- [3] McCloghrie, K., Perkins, D., and J. Schoenwaelder, "Conformance Statements for SMIv2", STD 58, RFC 2580, April 1999.

7.2. Informative References

[4] Case, J., Mundy, R., Partain, D., and B. Stewart, "Introduction and Applicability Statements for Internet-Standard Management Framework", <u>RFC 3410</u>, December 2002.

Authors' Addresses

Heiko Gerstung Meinberg Funkuhren Gmbh & Co. KG Auf der Landwehr 22 Bad Pyrmont 31812 Germany

Phone: +49 5281 9309 29

Email: heiko.gerstung@meinberg.de

Chris Elliott Cisco Systems, Inc. 7025 Kit Creek Rd., P.O. Box 14987 Research Triangle Park 27709 USA

Phone: +1 919-392-2146 Email: chelliot@cisco.com

Full Copyright Statement

Copyright (C) The IETF Trust (2007).

This document is subject to the rights, licenses and restrictions contained in $\underline{\mathsf{BCP}}$ 78, and except as set forth therein, the authors retain all their rights.

This document and the information contained herein are provided on an "AS IS" basis and THE CONTRIBUTOR, THE ORGANIZATION HE/SHE REPRESENTS OR IS SPONSORED BY (IF ANY), THE INTERNET SOCIETY, THE IETF TRUST AND THE INTERNET ENGINEERING TASK FORCE DISCLAIM ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTY THAT THE USE OF THE INFORMATION HEREIN WILL NOT INFRINGE ANY RIGHTS OR ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

Intellectual Property

The IETF takes no position regarding the validity or scope of any Intellectual Property Rights or other rights that might be claimed to pertain to the implementation or use of the technology described in this document or the extent to which any license under such rights might or might not be available; nor does it represent that it has made any independent effort to identify any such rights. Information on the procedures with respect to rights in RFC documents can be found in $\underline{\mathsf{BCP}}$ 78 and $\underline{\mathsf{BCP}}$ 79.

Copies of IPR disclosures made to the IETF Secretariat and any assurances of licenses to be made available, or the result of an attempt made to obtain a general license or permission for the use of such proprietary rights by implementers or users of this specification can be obtained from the IETF on-line IPR repository at http://www.ietf.org/ipr.

The IETF invites any interested party to bring to its attention any copyrights, patents or patent applications, or other proprietary rights that may cover technology that may be required to implement this standard. Please address the information to the IETF at ietf-ipr@ietf.org.

Acknowledgment

Funding for the RFC Editor function is provided by the IETF Administrative Support Activity (IASA).