

Expires December 2000

19 June 2000

Management Information Base for the PINT Services Architecture

<[draft-ietf-pint-mib-02.txt](#)>

Abstract

This memo describes a proposed MIB for the PINT Services Architecture.

Status of this Memo

This document is an Internet-Draft and is in full conformance with all provisions of [Section 10 of RFC 2026](#). Internet-Drafts are working documents of the Internet Engineering Task Force (IETF), its areas, and its working groups. Note that other groups may also distribute working documents as Internet- Drafts.

Internet-Drafts are draft documents valid for a maximum of six months and may be updated, replaced, or obsoleted by other documents at any time. It is inappropriate to use Internet Drafts as reference material or to cite them other than as "work in progress."

The list of current Internet-Drafts can be accessed at <http://www.ietf.org/ietf/1id-abstracts.txt>

The list of Internet-Draft Shadow Directories can be accessed at <http://www.ietf.org/shadow.html>.

1. Introduction

PINT services are an emerging set of new Internet based applications where voice (and fax) requests to the PSTN (Public Switched Telephone Network) are carried over the Internet. [RFC 2458](#) [[1](#)] gives a good

introduction to the (pre-standard) PINT architecture and services. It also has examples of some of the early implementations of pre-PINT.

This document defines a MIB which contains the elements for monitoring the performance of a PINT based service. The MIB consists of details of the four basic PINT services and their performance statistics measured under various criteria.

It is not the purpose of this MIB to enable management of the PINT networking elements. We are concerned only with the PINT specific performance parameters. While it is understood that PINT service performance is closely related to host and network performance, they are not addressed here.

2. The SNMP Management Framework

The SNMP Management Framework presently consists of five major components:

- o An overall architecture, described in [RFC 2571](#) [2].
- o Mechanisms for describing and naming objects and events for the purpose of management. The first version of this Structure of Management Information (SMI) is called SMIV1 and described in [RFC 1155](#) [3], [RFC 1212](#) [4] and [RFC 1215](#) [5]. The second version, called SMIV2, is described in [RFC 2578](#) [6], [RFC 2579](#) [7] and [RFC 2580](#) [8].
- o Message protocols for transferring management information. The first version of the SNMP message protocol is called SNMPv1 and described in [RFC 1157](#) [9]. A second version of the SNMP message protocol, which is not an Internet standards track protocol, is called SNMPv2c and described in [RFC 1901](#) [10] and [RFC 1906](#) [11]. The third version of the message protocol is called SNMPv3 and described in [RFC 1906](#) [11], [RFC 2572](#) [12] and [RFC 2574](#) [13].
- o Protocol operations for accessing management information. The first set of protocol operations and associated PDU formats is described in [RFC 1157](#) [9]. A second set of protocol operations and associated PDU formats is described in [RFC 1905](#) [14].
- o A set of fundamental applications described in [RFC 2573](#) [15]

and the view-based access control mechanism described in [RFC 2575](#) [16].

A more detailed introduction to the current SNMP Management Framework can be found in [RFC 2570](#) [17].

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. Objects in the MIB are defined using the mechanisms defined in the SMI.

This memo specifies a MIB module that is compliant to the SMIV2. A MIB conforming to the SMIV1 can be produced through the appropriate translations. The resulting translated MIB must be semantically equivalent, except where objects or events are omitted because no translation is possible (use of Counter64). Some machine-readable information in SMIV2 will be converted into textual descriptions in SMIV1 during the translation process. However, this loss of machine readable information is not considered to change the semantics of the MIB.

[3.](#) The need for PINT services monitoring MIB

Traditionally voice (and fax) requests originate and terminate inside a PSTN network. This network is well known for robust handling of the requests, in terms of availability and security. However when the requests originate from the Internet there is a concern both on the part of the user as well as the provider about issues like reliable forwarding of the call requests to the PINT gateway under various network conditions, user/host authentication, secure handling of the user information etc. Performance and security management becomes all the more important where PINT services cross multiple administrative domains (or providers).

This MIB is an attempt to list the parameters that need to be monitored on an user, PINT client, PINT server and PINT gateway basis.

(PINT services, their invocation methods/protocols and security issues associated with the PINT architecture are discussed in detail in [\[18\]](#)).

[4.](#) PINT MIB - Overview

Following is a list of some explanations on the MIB definitions that we have chosen to construct.

- o The basic purpose of this MIB is to monitor the access to PINT services both from the performance and security point of view. Information may pertain to a certain user or his/her system (PINT client) or the system providing the PINT services (PINT server) or the PINT gateway that forwards the call to the PSTN network.
- o We propose to build the configuration table as an extension of the Application MIB - [RFC 2287](#) [19] using the augments construct. Server location and contact might be retrieved from the standard MIB-II sysLocation and sysContact objects. There is no need to replicate this information in the PINT MIB. However, the PINT administrator may be a different person than the sysadmin with global responsibilities, thus a pintSysContact object is defined.
- o We chose to monitor the gateway connections from the PINT server. While the agent runs in the PINT servers, the connections to the gateways might need to be monitored in order to understand what goes on. We placed them in a separate MIB group, and by using MODULE-COMPLIANCE clauses, agents that cannot implement this stuff will not be mandated to do it.
- o There is no traps definition in this preliminary proposal. Note that thresholding on counters is always possible by using a standard mechanism defined by the Remote Monitoring MIB, that can be referenced here. Some events that may be defined by using this mechanisms:
 - * continuous login/authentication failure or refusal from a particular client or user
 - * nuisance call - repeated calls (within a specified period) to a number originating from the same user
- o The client performance and user performance tables may be rather resource demanding for an agent implementation. In some MIBs, like the Remote Monitoring (RMON) MIBs, control mechanisms were built in order to activate those statistics on demand. If needed, a sorting ('topN') mechanism can be designed, so that a

sorted view of clients or users is presented for the high level debugging.

- o We built a time-distribution trying to cover both short-lived, as well as longer sessions (1-10 secs, 10 secs - 1 min., 1-15 min., 15 mins-24 hours, longer).
- o PintServerClientAddress is defined as a SnmpAdminString. It may include an IpAddress and/or name, but we preferred to minimize the number of indices at this stage, and keep a human-readable format at the same time.
- o We define pintServerUserIdName as the UserId. This UserId needs to be unique across multiple PINT servers and gateways (depending on the architecture) and is mapped to the SessionId. One way to achieve this uniqueness is by appending clientId to the UserId string before sending to the PINT server. The SessionId could then be a combination of this new UserId and a timestamp.

5. Definitions

PINT-MIB DEFINITIONS ::= BEGIN

IMPORTS

OBJECT-TYPE, Counter32, MODULE-IDENTITY, mib-2
FROM SNMPv2-SMI
TEXTUAL-CONVENTION
FROM SNMPv2-TC
MODULE-COMPLIANCE, OBJECT-GROUP
FROM SNMPv2-CONF
SysApplInstallPkgIndex
FROM SYSAPPL-MIB
SnmpAdminString
FROM SNMP-FRAMEWORK-MIB; -- [RFC 2271](#) [[20](#)]

pintMib MODULE-IDENTITY
LAST-UPDATED "9908310732Z"
ORGANIZATION "Lucent Technologies"
CONTACT-INFO
"Murali Krishnaswamy
Postal: 3C-512, 101 Crawfords Corner Rd.

Holmdel, NJ 07733
Tel: +1 (732)949-3611
FAX: +1 (732)949-3210
E-mail: murali@lucent.com

Dan Romascanu
Postal: Atidim Technology Park, Bldg 3
Tel Aviv, Israel
Tel: +972 3 6458414
E-mail: dromasca@lucent.com"

DESCRIPTION

"This MIB defines the objects necessary to monitor
PINT Services"

REVISION "9909161200Z"

DESCRIPTION

"Initial version, published as RFC xxxx."

::= { mib-2 99999 } -- Not an IANA number

PintServiceType ::= TEXTUAL-CONVENTION

SYNTAX INTEGER {
R2C(1), -- Request-to-Talk
R2F(2), -- Request-to-Fax
R2FB(3), -- Request-to-Fax-Back
R2HC(4) -- Request-to-Hear-Content
}

PintPerfStatPeriod ::= TEXTUAL-CONVENTION

SYNTAX INTEGER {
Last30sec(1), -- Performance Statics for the last 30 sec
Last15min(2), -- 15 min
Last24Hr(3), -- 24 Hour
SinceReboot(4) -- Since the time the pint server was
-- last rebooted
}

DESCRIPTION

"Note that the values of the counters indexed with a value
SinceReboot(4) can be potentially affected by a counter rollover.
It is the responsibility of the application using this object to
take into account that the counter has been zeroed each time it
reached a value of (2**32-1)."

pintServerConfig OBJECT IDENTIFIER ::= { pintMib 1 }
pintServerMonitor OBJECT IDENTIFIER ::= { pintMib 2 }
pintMibConformance OBJECT IDENTIFIER ::= { pintMib 3 }

-- pintServerConfig - PINT configuration MIB variables

```
pintReleaseNumber OBJECT-TYPE
    SYNTAX      SnmpAdminString
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "An indication of version of the PINT protocol supported
        by this agent."
 ::= { pintServerConfig 1 }
```

```
pintSysContact          OBJECT-TYPE
    SYNTAX      SnmpAdminString
    MAX-ACCESS  read-write
    STATUS      current
    DESCRIPTION
        "Contact information related to the administration of the PINT
        services."
 ::= { pintServerConfig 2 }
```

```
pintApplInstallPkgTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF PintApplInstallPkgEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "Table describing the PINT applications that are installed."
 ::= { pintServerConfig 3 }
```

```
pintApplInstallPkgEntry OBJECT-TYPE
    SYNTAX      PintApplInstallPkgEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "Entries per PINT Application."
    AUGMENTS { sysApplInstallPkgIndex }
 ::= { pintApplInstallPkgTable 1 }
```

```
PintApplInstallPkgEntry ::= SEQUENCE {
    pintApplInstallPkgDescription  SnmpAdminString
}
```

```
pintApplInstallPkgDescription OBJECT-TYPE
    SYNTAX      SnmpAdminString
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "Textual description of the installed PINT application."
 ::= { pintApplInstallPkgEntry 1 }
```


pintRegisteredGatewayTable OBJECT-TYPE

SYNTAX SEQUENCE OF PintRegisteredGatewayEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"Table describing the registered gateway applications."

::= { pintServerConfig 4 }

pintRegisteredGatewayEntry OBJECT-TYPE

SYNTAX PintRegisteredGatewayEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"Entries per Registered Gateway Application."

AUGMENTS { sysApplInstallPkgIndex, pintRegisteredGatewayName }

::= { pintRegisteredGatewayTable 1 }

pintRegisteredGatewayEntry ::= SEQUENCE {

pintRegisteredGatewayName SnmpAdminString

pintRegisteredGatewayDescription SnmpAdminString

}

pintRegisteredGatewayName OBJECT-TYPE

SYNTAX SnmpAdminString

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"Name of the registered gateway."

::= { pintRegisteredGatewayEntry 1 }

pintRegisteredGatewayDescription OBJECT-TYPE

SYNTAX SnmpAdminString

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Textual description of the registered gateway."

::= { pintRegisteredGatewayEntry 2 }

-- pintServerMonitor - PINT monitoring statistics MIB variables

pintServerGlobalPerf OBJECT IDENTIFIER ::= {pintServerMonitor 1 }

pintServerClientPerf OBJECT IDENTIFIER ::= {pintServerMonitor 2 }

pintServerUserIdPerf OBJECT IDENTIFIER ::= {pintServerMonitor 3 }

pintServerGatewayPerf OBJECT IDENTIFIER ::= {pintServerMonitor 4 }


```
pintServerGlobalStatsTable      OBJECT-TYPE
    SYNTAX          SEQUENCE OF PintServerGlobalStatsEntry
    MAX-ACCESS      not-accessible
    STATUS          current
    DESCRIPTION
        "Table displaying the monitored global server statistics."
 ::= { pintServerGlobalPerf 1 }

pintServerGlobalStatsEntry OBJECT-TYPE
    SYNTAX          PintServerGlobalStatsEntry
    MAX-ACCESS      not-accessible
    STATUS          current
    DESCRIPTION
        "Entries in the global statistics table.
        One entry is defined for each monitored service type and
        performance statistics collection period."
        INDEX {pintServerServiceTypeIndex, pintServerPerfStatPeriodIndex}
 ::= { pintServerGlobalStatsTable 1 }

PintServerGlobalStatsEntry      ::= SEQUENCE {
pintServerServiceTypeIndex      PintServiceType,
pintServerPerfStatPeriodIndex   PintPerfStatPeriod,
pintServerGlobalCallsReceived   Counter32,
pintServerGlobalSuccessfulCalls Counter32,
pintServerGlobalDisconnectedCalls Counter32,
pintServerGlobalDisconnectedClientUserAuthorizationFailureCalls
                                Counter32,
pintServerGlobalDisconnectedServerProblemCalls Counter32,
pintServerGlobalDisconnectedGatewayProblemCalls Counter32
}

pintServerServiceTypeIndex OBJECT-TYPE
    SYNTAX          PintServiceType
    MAX-ACCESS      not-accessible
    STATUS          current
    DESCRIPTION
        "The unique identifier of the monitored service."
 ::= { pintServerGlobalStatsEntry 1 }

pintServerPerfStatPeriodIndex OBJECT-TYPE
    SYNTAX          PintPerfStatPeriod
    MAX-ACCESS      not-accessible
    STATUS          current
    DESCRIPTION
        "Time period for which the performance statistics are requested
        from the pint server."
 ::= { pintServerGlobalStatsEntry 2 }
```


pintServerGlobalCallsReceived OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of received global calls."

::= { pintServerGlobalStatsEntry 3 }

pintServerGlobalSuccessfulCalls OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of global successful calls."

::= { pintServerGlobalStatsEntry 4 }

pintServerGlobalDisconnectedCalls OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of global disconnected (failed) calls."

::= { pintServerGlobalStatsEntry 5 }

pintServerGlobalDisconnectedClientUserAuthorizationFailureCalls
OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of global calls that were disconnected because of client
or user authorization failure."

::= { pintServerGlobalStatsEntry 6 }

pintServerGlobalDisconnectedServerProblemCalls OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of global calls that were disconnected because of
server problems."

::= { pintServerGlobalStatsEntry 7 }

pintServerGlobalDisconnectedGatewayProblemCalls OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of global calls that were disconnected because of gateway problems."

::= { pintServerGlobalStatsEntry 8 }

pintServerClientStatsTable OBJECT-TYPE

SYNTAX SEQUENCE OF PintServerClientStatsEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"Table displaying the monitored server client statistics."

::= { pintServerClientPerf 1 }

pintServerClientStatsEntry OBJECT-TYPE

SYNTAX PintServerClientStatsEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"Entries in the client server statistics table.

One entry is defined for each client identified by name, monitored service type and performance statistics collection period."

INDEX {pintServerClientAddress, pintServerServiceTypeIndex,
pintServerPerfStatPeriodIndex}

::= { pintServerClientStatsTable 1 }

PintServerClientStatsEntry ::= SEQUENCE {

pintServerClientAddress SnmpAdminString,

pintServerClientCallsReceived Counter32,

pintServerClientSuccessfulCalls Counter32,

pintServerClientDisconnectedCalls Counter32,

pintServerClientDisconnectedClientAuthorizationFailureCalls
Counter32,

pintServerClientDisconnectedEgressFacilityProblemCalls Counter32

}

pintServerClientAddress OBJECT-TYPE

SYNTAX SnmpAdminString

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"The unique identifier of the monitored client

identified by its address represented as as a string."
 ::= { pintServerClientStatsEntry 1 }

pintServerClientCallsReceived OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of calls received from the specific client."

::= { pintServerClientStatsEntry 2 }

pintServerClientSuccessfulCalls OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of calls from the client successfully completed."

::= { pintServerClientStatsEntry 3 }

pintServerClientDisconnectedCalls OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of calls received from the client, and that were
 disconnected (failed)."

::= { pintServerClientStatsEntry 4 }

pintServerClientDisconnectedClientAuthorizationFailureCalls
 OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of calls from the client that were disconnected because of
 client authorization failure."

::= { pintServerClientStatsEntry 5 }

pintServerClientDisconnectedEgressFacilityProblemCalls OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of calls from the client that were disconnected because
 of egress facility problems."

::= { pintServerClientStatsEntry 6 }


```
pintServerUserIdStatsTable      OBJECT-TYPE
    SYNTAX          SEQUENCE OF PintServerUserIdStatsEntry
    MAX-ACCESS      not-accessible
    STATUS          current
    DESCRIPTION
        "Table displaying the monitored Pint service user statistics."
    ::= { pintServerUserIdPerf 1 }

pintServerUserIdStatsEntry OBJECT-TYPE
    SYNTAX          PintServerUserIdStatsEntry
    MAX-ACCESS      not-accessible
    STATUS          current
    DESCRIPTION
        "Entries in the user statistics table.
        One entry is defined for each user identified by name,
        each monitored service type and performance statistics collection
        period."
    INDEX {pintServerUserIdName, pintServerServiceTypeIndex,
          pintServerPerfStatPeriodIndex}
    ::= { pintServerUserIdStatsTable 1 }

PintServerUserIdStatsEntry      ::= SEQUENCE {
    pintServerUserIdName          UserIdName,
    pintServerUserIdCallsReceived Counter32,
    pintServerUserIdSuccessfulCalls Counter32,
    pintServerUserIdDisconnectedCalls Counter32,
    pintServerUserIdDisconnectedUserIdAuthorizationFailureCalls
                                                Counter32,
    pintServerUserIdDisconnectedEgressFacilityProblemCalls Counter32
}

pintServerUserIdName OBJECT-TYPE
    SYNTAX          SnmpAdminString
    MAX-ACCESS      not-accessible
    STATUS          current
    DESCRIPTION
        "The unique identifier of the monitored user
        identified by its name."
    ::= { pintServerUserIdStatsEntry 1 }

pintServerUserIdCallsReceived OBJECT-TYPE
    SYNTAX          Counter32
    MAX-ACCESS      read-only
    STATUS          current
    DESCRIPTION
        "Number of calls received from the specific user."
    ::= { pintServerUserIdStatsEntry 2 }
```


pintServerUserIdSuccessfulCalls OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of calls from the user successfully completed."

::= { pintServerUserIdStatsEntry 3 }

pintServerUserIdDisconnectedCalls OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of calls received from the user that were disconnected (failed)."

::= { pintServerUserIdStatsEntry 4 }

pintServerUserIdDisconnectedUserIdUserAuthorizationFailureCalls
OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of calls from the user that were disconnected because of user authorization failure."

::= { pintServerUserIdStatsEntry 5 }

pintServerUserIdDisconnectedEgressFacilityProblemCalls OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of calls from the user that were disconnected because of egress facility problems."

::= { pintServerUserIdStatsEntry 6 }

pintServerGatewayStatsTable OBJECT-TYPE

SYNTAX SEQUENCE OF PintServerGatewayStatsEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"Table displaying the monitored gateway statistics."

::= { pintServerGatewayPerf 1 }

pintServerGatewayStatsEntry OBJECT-TYPE

SYNTAX PintServerGatewayStatsEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"Entries in the gateway table.

One entry is defined for each gateway identified by name,
each monitored service type and performance statistics collection
period."

INDEX { pintRegisteredGatewayName, pintServerServiceTypeIndex,
pintServerPerfStatPeriodIndex
::= { pintServerGatewayStatsTable 1 }

PintServerGatewayStatsEntry ::= SEQUENCE {
pintServerGatewayCallsReceived Counter32,
pintServerGatewaySuccessfulCalls Counter32,
pintServerGatewayDisconnectedCalls Counter32
}

pintServerGatewayCallsReceived OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of calls received at the specified gateway."

::= { pintServerGatewayStatsEntry 1 }

pintServerGatewaySuccessfulCalls OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of calls successfully completed at the specified gateway."

::= { pintServerGatewayStatsEntry 2 }

pintServerGatewayDisconnectedCalls OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Number of calls that were disconnected (failed) at the specified
gateway."

::= { pintServerGatewayStatsEntry 3 }

--


```
-- Notifications Section
-- (none defined)
--
```

```
--
-- Conformance Section
--
```

```
pintMibCompliances OBJECT IDENTIFIER ::= { pintMibConformance 1 }
pintMibGroups       OBJECT IDENTIFIER ::= { pintMibConformance 2 }
```

```
pintMibCompliance MODULE-COMPLIANCE
    STATUS current
    DESCRIPTION
        "Describes the requirements for conformance to the
        PINT MIB."
    MODULE -- this module
    MANDATORY-GROUPS { pintMibConfigGroup, pintMibMonitorGroup }
    ::= { pintMibCompliances 1 }
```

```
pintMibConfigGroup OBJECT-GROUP
    OBJECTS {
        pintReleaseNumber,
        pintSysContact,
        pintApplInstallPkgDescription,
        pintRegisteredGatewayName,
        pintRegisteredGatewayDescription
    }
    STATUS current
    DESCRIPTION
        "A collection of objects providing configuration
information
        for a PINT Server."
    ::= { pintMibGroups 1 }
```

```
pintMibMonitorGroup OBJECT-GROUP
    OBJECTS {
pintServerServiceTypeIndex,
pintServerPerfStatPeriodIndex,
pintServerGlobalCallsReceived,
pintServerGlobalSuccessfulCalls,
pintServerGlobalDisconnectedCalls,
pintServerGlobalDisconnectedClientUserAuthorizationFailureCalls,
pintServerGlobalDisconnectedServerProblemCalls,
pintServerGlobalDisconnectedGatewayProblemCalls,
pintServerClientAddress,
pintServerClientCallsReceived,
pintServerClientSuccessfulCalls,
```



```
pintServerClientDisconnectedCalls,
pintServerClientDisconnectedClientAuthorizationFailureCalls,
pintServerClientDisconnectedEgressFacilityProblemCalls,
pintServerUserIdName,
pintServerUserIdCallsReceived,
pintServerUserIdSuccessfulCalls,
pintServerUserIdDisconnectedCalls,
pintServerUserIdDisconnectedUserIdAuthorizationFailureCalls,
pintServerUserIdDisconnectedEgressFacilityProblemCalls,
pintServerGatewayCallsReceived,
pintServerGatewaySuccessfulCalls,
pintServerGatewayDisconnectedCalls
    }
    STATUS    current
    DESCRIPTION
        "A collection of objects providing monitoring
information
        for a PINT Server."
    ::= { pintMibGroups 2 }
```

END

6. Acknowledgements

The authors would like to thank Igor Faynberg for his encouragement to produce this work.

7. Security Considerations

There is only one management object defined in this MIB that has a MAX-ACCESS clause of read-write (pintSysContact). There are no read-create objects. This read-write object may be considered sensitive or vulnerable in some network environments. The support for SET operations in a non-secure environment without proper protection can have a negative effect on network operations.

There are a number of managed objects in this MIB that may contain information that may be sensitive from a business perspective. One could be the customer identification (UserIdName). Also information on PINT services performance might itself be need to be guarded. It is thus important to control even GET access to these objects and possibly to even encrypt the values of these object when sending them over the network via SNMP. Not all versions of SNMP provide features for such a secure environment.

SNMPv1 by itself is not a secure environment. Even if the network itself is secure (for example by using IPSec), even then, there is no control as to who on the secure network is allowed to access and GET/SET (read/change/create/delete) the objects in this MIB.

It is recommended that the implementers consider the security features as provided by the SNMPv3 framework. Specifically, the use of the User-based Security Model [RFC 2574](#) [13] and the View-based Access Control Model [RFC 2575](#) [16] is recommended.

It is then a customer/user responsibility to ensure that the SNMP entity giving access to an instance of this MIB, is properly configured to give access to the objects only to those principals (users) that have legitimate rights to indeed GET or SET (change/create/delete) them.

8. IANA Considerations

All extensions to the values listed in this MIB must be done through Standards Action processes as defined in [RFC 2434](#) [21].

9. References

- [1] H.Lu, et. al, "Toward the PSTN/Internet Inter-Networking --Pre-PINT Implementations", [RFC 2458](#), November 1998.
- [2] Wijnen, B., Harrington, D., and Presuhn, R., "An Architecture for Describing SNMP Management Frameworks", [RFC 2571](#), April 1999.
- [3] Rose, M. and McCloghrie, K., "Structure and Identification of Management Information for TCP/IP-based Internets", [RFC 1155](#), May 1990.
- [4] Rose, M. and McCloghrie, K., "Concise MIB Definitions", [RFC 1212](#), March 1991.
- [5] Rose, M., "A Convention for Defining Traps for use with the SNMP", [RFC 1215](#), March 1991.
- [6] McCloghrie, K., Perkins, D., and Schoenwaelder, J., "Structure of Management Information Version 2 (SMIv2)", [RFC 2578](#), April 1999.
- [7] McCloghrie, K., Perkins, D., and Schoenwaelder, J., "Textual Conventions for SMIv2", [RFC 2579](#), April 1999.

- [8] McCloghrie, K., Perkins, D., and Schoenwaelder, J., "Conformance Statements for SMIV2", [RFC 2580](#), April 1999.
- [9] Case, J., Fedor, M., Schoffstall, M., and Davin, J., "Simple Network Management Protocol", [RFC 1157](#), May 1990.
- [10] Case, J., McCloghrie, K., Rose, M., and Waldbusser, S., "Introduction to Community-based SNMPv2", [RFC 1901](#), January 1996.
- [11] Case, J., McCloghrie, K., Rose, M., and Waldbusser, S., "Transport Mappings for Version 2 of the Simple Network Management Protocol (SNMPv2)", [RFC 1906](#), January 1996.
- [12] Case, J., Harrington D., Presuhn R., and Wijnen, B., "Message Processing and Dispatching for the Simple Network Management Protocol (SNMP)", [RFC 2572](#), April 1999.
- [13] Blumenthal, U. and Wijnen, B., "User-based Security Model (USM) for version 3 of the Simple Network Management Protocol (SNMPv3)", [RFC 2574](#), April 1999.
- [14] Case, J., McCloghrie, K., Rose, M., and Waldbusser, S., "Protocol Operations for Version 2 of the Simple Network Management Protocol (SNMPv2)", [RFC 1905](#), January 1996.
- [15] Levi, D., Meyer, P., and Stewart, B., "SNMPv3 Applications", [RFC 2573](#), April 1999.
- [16] Wijnen, B., Presuhn, R., and K. McCloghrie, "View-based Access Control Model (VACM) for the Simple Network Management Protocol (SNMP)", [RFC 2575](#), April 1999.
- [17] Case, J., Mundy, R., Partain, D., and B. Stewart, "Introduction to Version 3 of the Internet-standard Network Management Framework", [RFC 2570](#), April 1999.
- [18] S. Petrack, L. Conroy, "The PINT Service Protocol: Extensions to SIP and SDP for IP Access to Telephone Call Services", [draft-ietf-pint-protocol-01.txt](#), 14 July 1999.
- [19] C. Krupczak, J. Saperia, "Definitions of System-Level Managed Objects for Applications", [RFC 2287](#), February 1998.
- [20] D. Harrington, R. Presuhn, B. Wijnen, "An Architecture for Describing SNMP Management Frameworks", [RFC 2271](#), January 1998.

- [21] T. Narten, H. Alvestrand, "Guidelines for Writing an IANA Considerations Section in RFCs", [RFC 2434](#), October 1998.

10. Authors' Addresses

Murali Krishnaswamy
Lucent Technologies
3C-512, 101 Crawfords Corner Rd.
Holmdel, NJ 07733
Tel: +1 (732)949-3611
Fax: +1 (732)949-3210
E-mail: murali@lucent.com

Dan Romascanu
Lucent Technologies
Atidim Technology Park, Bldg 3
Tel Aviv, Israel
Tel: +972 3 6458414
E-mail: dromasca@lucent.com

