

MASQUE
Internet-Draft
Intended status: Experimental
Expires: 6 September 2022

T. Pauly
Apple Inc.
D. Schinazi
Google LLC
5 March 2022

QUIC-Aware Proxying Using HTTP
draft-pauly-masque-quic-proxy-03

Abstract

This document defines an extension to UDP Proxying over HTTP that adds specific optimizations for proxied QUIC connections. This extension allows a proxy to reuse UDP 4-tuples for multiple connections. It also defines a mode of proxying in which QUIC short header packets can be forwarded using an HTTP/3 proxy rather than being re-encapsulated and re-encrypted.

Discussion Venues

This note is to be removed before publishing as an RFC.

Source for this draft and an issue tracker can be found at <https://github.com/tfpaully/quic-proxy> (<https://github.com/tfpaully/quic-proxy>).

Status of This Memo

This Internet-Draft is submitted in full conformance with the provisions of [BCP 78](#) and [BCP 79](#).

Internet-Drafts are working documents of the Internet Engineering Task Force (IETF). Note that other groups may also distribute working documents as Internet-Drafts. The list of current Internet-Drafts is at <https://datatracker.ietf.org/drafts/current/>.

Internet-Drafts are draft documents valid for a maximum of six months and may be updated, replaced, or obsoleted by other documents at any time. It is inappropriate to use Internet-Drafts as reference material or to cite them other than as "work in progress."

This Internet-Draft will expire on 6 September 2022.

Copyright Notice

Copyright (c) 2022 IETF Trust and the persons identified as the document authors. All rights reserved.

Internet-Draft

QUIC Proxy

March 2022

This document is subject to [BCP 78](#) and the IETF Trust's Legal Provisions Relating to IETF Documents (<https://trustee.ietf.org/license-info>) in effect on the date of publication of this document. Please review these documents carefully, as they describe your rights and restrictions with respect to this document. Code Components extracted from this document must include Revised BSD License text as described in Section 4.e of the [Trust Legal Provisions](#) and are provided without warranty as described in the Revised BSD License.

Table of Contents

1.	Introduction	2
1.1.	Conventions and Definitions	4
1.2.	Terminology	4
2.	Required Proxy State	5
2.1.	Stream Mapping	5
2.2.	Target Connection ID Mapping	5
2.3.	Client Connection ID Mappings	6
2.4.	Detecting Connection ID Conflicts	6
3.	Connection ID Capsule Types	7
4.	Client Request Behavior	8
4.1.	New Proxied Connection Setup	9
4.2.	Adding New Client Connection IDs	9
4.3.	Sending With Forwarded Mode	9
4.4.	Receiving With Forwarded Mode	10
5.	Proxy Response Behavior	11
5.1.	Removing Mapping State	12
5.2.	Handling Connection Migration	13
6.	Example	13
7.	Interactions with Load Balancers	15
8.	Packet Size Considerations	15
9.	Security Considerations	16
10.	IANA Considerations	16
10.1.	HTTP Header	16
10.2.	Capsule Types	17
11.	References	17
11.1.	Normative References	17
11.2.	Informative References	18
	Acknowledgments	18
	Authors' Addresses	18

[1.](#) Introduction

UDP Proxying over HTTP [[CONNECT-UDP](#)] defines a way to send datagrams through an HTTP proxy, where UDP is used to communicate between the proxy and a target server. This can be used to proxy QUIC connections [[QUIC](#)], since QUIC runs over UDP datagrams.

This document uses the term "target" to refer to the server that a client is accessing via a proxy. This target may be an origin hosting content, or another proxy.

This document extends the UDP proxying protocol to add signalling about QUIC Connection IDs. QUIC Connection IDs are used to identify QUIC connections in scenarios where there is not a strict bidirectional mapping between one QUIC connection and one UDP 4-tuple (pairs of IP addresses and ports). A proxy that is aware of Connection IDs can reuse UDP 4-tuples between itself and a target for multiple proxied QUIC connections.

Awareness of Connection IDs also allows a proxy to avoid re-encapsulation and re-encryption of proxied QUIC packets once a connection has been established. When this functionality is present, the proxy can support two modes for handling QUIC packets:

1. Tunnelled, in which client <-> target QUIC packets are encapsulated inside client <-> proxy QUIC packets. These packets use multiple layers of encryption and congestion control. QUIC long header packets MUST use this mode. QUIC short header packets MAY use this mode. This is the default mode for UDP proxying.
2. Forwarded, in which client <-> target QUIC packets are sent directly over the client <-> proxy UDP socket. These packets are only encrypted using the client-target keys, and use the client-target congestion control. This mode MUST only be used for QUIC short header packets.

Forwarding is defined as an optimization to reduce CPU processing on clients and proxies, as well as avoiding MTU overhead for packets on the wire. This makes it suitable for deployment situations that otherwise relied on cleartext TCP proxies, which cannot support QUIC and have inferior security and privacy properties.

The properties provided by the forwarding mode are as follows:

- * All packets sent between the client and the target traverse through the proxy device.
- * The target server cannot know the IP address of the client solely based on the proxied packets the target receives.
- * Observers of either or both of the client <-> proxy link and the proxy <-> target are not able to learn more about the client <-> target communication than if no proxy was used.

It is not a goal of forwarding mode to prevent correlation between client <-> proxy and the proxy <-> target packets from an entity that can observe both links. See [Section 9](#) for further discussion.

Both clients and proxies can unilaterally choose to disable forwarded mode for any client <-> target connection.

The forwarding mode of this extension is only defined for HTTP/3 [[HTTP3](#)] and not any earlier versions of HTTP. The forwarding mode also requires special handling in order to be compatible with intermediaries or load balancers (see [Section 7](#)).

QUIC proxies only need to understand the Header Form bit, and the connection ID fields from packets in client <-> target QUIC connections. Since these fields are all in the QUIC invariants header [[INVARIANTS](#)], QUIC proxies can proxy all versions of QUIC.

[1.1](#). Conventions and Definitions

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "NOT RECOMMENDED", "MAY", and "OPTIONAL" in this document are to be interpreted as described in [BCP 14](#) [[RFC2119](#)] [[RFC8174](#)] when, and only when, they appear in all capitals, as shown here.

[1.2](#). Terminology

This document uses the following terms:

- * Client: the client of all QUIC connections discussed in this document.
- * Proxy: the endpoint that responds to the UDP proxying request.
- * Target: the server that a client is accessing via a proxy.
- * Client <-> Proxy QUIC connection: a single QUIC connection established from the client to the proxy.
- * Socket: a UDP 4-tuple (local IP address, local UDP port, remote IP address, remote UDP port). In some implementations, this is referred to as a "connected" socket.
- * Client-facing socket: the socket used to communicate between the client and the proxy.
- * Target-facing socket: the socket used to communicate between the proxy and the target.

- * Client Connection ID: a QUIC Connection ID that is chosen by the client, and is used in the Destination Connection ID field of packets from the target to the client.
- * Target Connection ID: a QUIC Connection ID that is chosen by the target, and is used in the Destination Connection ID field of packets from the client to the target.

[2.](#) Required Proxy State

In the methods defined in this document, the proxy is aware of the QUIC Connection IDs being used by proxied connections, along with the sockets used to communicate with the client and the target. Tracking Connection IDs in this way allows the proxy to reuse target-facing sockets for multiple connections and support the forwarding mode of proxying.

QUIC packets can be either tunnelled within an HTTP proxy connection using HTTP Datagram frames [[HTTP-DGRAM](#)], or be forwarded directly alongside an HTTP/3 proxy connection on the same set of IP addresses and UDP ports. The use of forwarded mode requires the consent of both the client and the proxy.

In order to correctly route QUIC packets in both tunnelled and forwarded modes, the proxy needs to maintain mappings between several items. There are three required unidirectional mappings, described below.

[2.1.](#) Stream Mapping

Each pair of client <-> proxy QUIC connection and an HTTP stream MUST be mapped to a single target-facing socket.

(Client <-> Proxy QUIC connection + Stream)
=> Target-facing socket

Multiple streams can map to the same target-facing socket, but a single stream cannot be mapped to multiple target-facing sockets.

This mapping guarantees that any HTTP Datagram using a stream sent from the client to the proxy in tunnelled mode can be sent to the correct target.

[2.2.](#) Target Connection ID Mapping

Each pair of Target Connection ID and client-facing socket MUST map to a single target-facing socket.

(Client-facing socket + Target Connection ID)
=> Target-facing socket

Multiple pairs of Connection IDs and sockets can map to the same target-facing socket.

This mapping guarantees that any QUIC packet containing the Target Connection ID sent from the client to the proxy in forwarded mode can be sent to the correct target. Thus, a proxy that does not allow forwarded mode does not need to maintain this mapping.

[2.3.](#) Client Connection ID Mappings

Each pair of Client Connection ID and target-facing socket MUST map to a single stream on a single client <-> proxy QUIC connection.

Additionally, the pair of Client Connection ID and target-facing socket MUST map to a single client-facing socket.

(Target-facing socket + Client Connection ID)
=> (Client <-> Proxy QUIC connection + Stream)
(Target-facing socket + Client Connection ID)
=> Client-facing socket

Multiple pairs of Connection IDs and sockets can map to the same stream or client-facing socket.

These mappings guarantee that any QUIC packet sent from a target to the proxy can be sent to the correct client, in either tunnelled or forwarded mode. Note that this mapping becomes trivial if the proxy always opens a new target-facing socket for every client request with a unique stream. The mapping is critical for any case where target-facing sockets are shared or reused.

[2.4.](#) Detecting Connection ID Conflicts

In order to be able to route packets correctly in both tunnelled and forwarded mode, proxies check for conflicts before creating a new mapping. If a conflict is detected, the proxy will reject the client's request, as described in [Section 5](#).

Two sockets conflict if and only if all members of the 4-tuple (local IP address, local UDP port, remote IP address, and remote UDP port) are identical.

Two Connection IDs conflict if and only if one Connection ID is equal to or a prefix of another. For example, a zero-length Connection ID conflicts with all connection IDs. This definition of a conflict originates from the fact that QUIC short headers do not carry the

length of the Destination Connection ID field, and therefore if two short headers with different Destination Connection IDs are received on a shared socket, one being a prefix of the other prevents the receiver from identifying which mapping this corresponds to.

The proxy treats two mappings as being in conflict when a conflict is detected for all elements on the left side of the mapping diagrams above.

Since very short Connection IDs are more likely to lead to conflicts, particularly zero-length Connection IDs, a proxy MAY choose to reject all requests for very short Connection IDs as conflicts, in anticipation of future conflicts. Note that a request that doesn't contain any Connection ID is equivalent to a request for a zero-length Connection ID, and similarly would cause conflicts when forwarding.

[3.](#) Connection ID Capsule Types

Proxy awareness of QUIC Connection IDs relies on using capsules ([\[HTTP-DGRAM\]](#)) to signal the addition and removal of client and Target Connection IDs.

Note that these capsules do not register contexts. QUIC packets are encoded using HTTP Datagrams with the context ID set to zero as defined in [\[CONNECT-UDP\]](#).

The capsules used for QUIC-aware proxying allow a client to register connection IDs with the proxy, and for the proxy to acknowledge or reject the connection ID mappings.

The REGISTER_CLIENT_CID and REGISTER_TARGET_CID capsule types (see [Section 10.2](#) for the capsule type values) allow a client to inform the proxy about a new Client Connection ID or a new Target Connection ID, respectively. These capsule types MUST only be sent by a client.

The ACK_CLIENT_CID and ACK_TARGET_CID capsule types (see [Section 10.2](#) for the capsule type values) are sent by the proxy to the client to indicate that a mapping was successfully created for a registered connection ID. These capsule types MUST only be sent by a proxy.

The CLOSE_CLIENT_CID and CLOSE_TARGET_CID capsule types (see [Section 10.2](#) for the capsule type values) allow either a client or a proxy to remove a mapping for a connection ID. These capsule types MAY be sent by either a client or the proxy. If a proxy sends a CLOSE_CLIENT_CID without having sent an ACK_CLIENT_CID, or if a proxy sends a CLOSE_TARGET_CID without having sent an ACK_TARGET_CID, it is rejecting a Connection ID registration.

All Connection ID capsule types share the same format:

```

Connection ID Capsule {
  Type (i) = 0xffe100..0xffe103,
  Length (i),
  Connection ID (0..2040),
}

```

Figure 1: Connection ID Capsule Format

Connection ID: A connection ID being registered or acknowledged, which is between 0 and 255 bytes in length. The length of the connection ID is implied by the length of the capsule. Note that in QUICv1, the length of the Connection ID is limited to 20 bytes, but QUIC invariants allow up to 255 bytes.

4. Client Request Behavior

A client initiates UDP proxying via a CONNECT request as defined in [CONNECT-UDP]. Within its request, it includes the "Proxy-QUIC-Forwarding" header to indicate whether or not the request should support forwarding. If this header is not included, the client **MUST NOT** send any connection ID capsules.

The "Proxy-QUIC-Forwarding" is an Item Structured Header [RFC8941]. Its value **MUST** be a Boolean. Its ABNF is:

```
Proxy-QUIC-Forwarding = sf-boolean
```

If the client wants to enable QUIC packet forwarding for this request, it sets the value to "?1". If it doesn't want to enable forwarding, but instead only provide information about QUIC Connection IDs for the purpose of allowing the proxy to share a target-facing socket, it sets the value to "?0".

If the proxy supports QUIC-aware proxying, it will include the "Proxy-QUIC-Forwarding" header in successful HTTP responses. The value indicates whether or not the proxy supports forwarding. If the client does not receive this header in responses, the client **SHALL** assume that the proxy does not understand how to parse Connection ID capsules, and **MUST NOT** send any Connection ID capsules.

The client sends a REGISTER_CLIENT_CID capsule whenever it advertises a new Client Connection ID to the target, and a REGISTER_TARGET_CID capsule when it has received a new Target Connection ID for the target. Note that the initial REGISTER_CLIENT_CID capsule **MAY** be sent prior to receiving an HTTP response from the proxy.

[4.1.](#) New Proxied Connection Setup

To initiate QUIC-aware proxying, the client sends a REGISTER_CLIENT_CID capsule containing the initial Client Connection ID that the client has advertised to the target.

If the mapping is created successfully, the client will receive a ACK_CLIENT_CID capsule that contains the same connection ID that was requested.

Since clients are always aware whether or not they are using a QUIC proxy, clients are expected to cooperate with proxies in selecting Client Connection IDs. A proxy detects a conflict when it is not able to create a unique mapping using the Client Connection ID ([Section 2.4](#)). It can reject requests that would cause a conflict and indicate this to the client by replying with a CLOSE_CLIENT_CID capsule. In order to avoid conflicts, clients SHOULD select Client Connection IDs of at least 8 bytes in length with unpredictable values. A client also SHOULD NOT select a Client Connection ID that matches the ID used for the QUIC connection to the proxy, as this inherently creates a conflict.

If the rejection indicated a conflict due to the Client Connection ID, the client MUST select a new Connection ID before sending a new request, and generate a new packet. For example, if a client is sending a QUIC Initial packet and chooses a Connection ID that conflicts with an existing mapping to the same target server, it will need to generate a new QUIC Initial.

[4.2.](#) Adding New Client Connection IDs

Since QUIC connection IDs are chosen by the receiver, an endpoint needs to communicate its chosen connection IDs to its peer before the peer can start using them. In QUICv1, this is performed using the NEW_CONNECTION_ID frame.

Prior to informing the target of a new chosen client connection ID, the client MUST send a REGISTER_CLIENT_CID capsule request containing the new Client Connection ID.

The client should only inform the target of the new Client Connection ID once an ACK_CLIENT_CID capsule is received that contains the echoed connection ID.

[4.3.](#) Sending With Forwarded Mode

Support for forwarding mode is determined by the "Proxy-QUIC-Forwarding" header, see [Section 5](#).

Once the client has learned the target server's Connection ID, such as in the response to a QUIC Initial packet, it can send a REGISTER_TARGET_CID capsule containing the Target Connection ID to request the ability to forward packets.

The client MUST wait for an ACK_TARGET_CID capsule that contains the echoed connection ID before using forwarded mode.

Prior to receiving the proxy server response, the client MUST send short header packets tunnelled in HTTP Datagram frames. The client MAY also choose to tunnel some short header packets even after receiving the successful response.

If the Target Connection ID registration is rejected, for example with a CLOSE_TARGET_CID capsule, it MUST NOT forward packets to the requested Target Connection ID, but only use tunnelled mode. The request might also be rejected if the proxy does not support forwarded mode or has it disabled by policy.

QUIC long header packets MUST NOT be forwarded. These packets can only be tunnelled within HTTP Datagram frames to avoid exposing unnecessary connection metadata.

When forwarding, the client sends a QUIC packet with the target server's Connection ID in the QUIC short header, using the same socket between client and proxy that was used for the main QUIC connection between client and proxy.

[4.4](#). Receiving With Forwarded Mode

If the client has indicated support for forwarding with the "Proxy-QUIC-Forwarding" header, the proxy MAY use forwarded mode for any Client Connection ID for which it has a valid mapping.

Once a client has sent "Proxy-QUIC-Forwarding" with a value of "?1", it MUST be prepared to receive forwarded short header packets on the socket between itself and the proxy for any Client Connection ID that it has registered with a REGISTER_CLIENT_CID capsule. The client uses the Destination Connection ID field of the received packet to

determine if the packet was originated by the proxy, or merely forwarded from the target.

[5.](#) Proxy Response Behavior

Upon receipt of a CONNECT request that includes the "Proxy-QUIC-Forwarding" header, the proxy indicates to the client that it supports QUIC-aware proxying by including a "Proxy-QUIC-Forwarding" header in a successful response. If it supports QUIC packet forwarding, it sets the value to "?1"; otherwise, it sets it to "?0".

Upon receipt of a REGISTER_CLIENT_CID or REGISTER_TARGET_CID capsule, the proxy validates the registration, tries to establish the appropriate mappings as described in [Section 2](#).

The proxy MUST reply to each REGISTER_CLIENT_CID capsule with either an ACK_CLIENT_CID or CLOSE_CLIENT_CID capsule containing the Connection ID that was in the registration capsule.

Similarly, the proxy MUST reply to each REGISTER_TARGET_CID capsule with either an ACK_TARGET_CID or CLOSE_TARGET_CID capsule containing the Connection ID that was in the registration capsule.

The proxy then determines the target-facing socket to associate with the client's request. This will generally involve performing a DNS lookup for the target hostname in the CONNECT request, or finding an existing target-facing socket to the authority. The target-facing socket might already be open due to a previous request from this client, or another. If the socket is not already created, the proxy creates a new one. Proxies can choose to reuse target-facing sockets across multiple UDP proxying requests, or have a unique target-facing socket for every UDP proxying request.

If a proxy reuses target-facing sockets, it SHOULD store which authorities (which could be a domain name or IP address literal) are

being accessed over a particular target-facing socket so it can avoid performing a new DNS query and potentially choosing a different target server IP address which could map to a different target server.

Target-facing sockets MUST NOT be reused across QUIC and non-QUIC UDP proxy requests, since it might not be possible to correctly demultiplex or direct the traffic. Any packets received on a target-facing socket used for proxying QUIC that does not correspond to a known Connection ID MUST be dropped.

When the proxy receives a REGISTER_CLIENT_CID capsule, it is receiving a request to be able to route traffic back to the client using that Connection ID. If the pair of this Client Connection ID and the selected target-facing socket does not create a conflict, the proxy creates the mapping and responds with a ACK_CLIENT_CID capsule.

After this point, any packets received by the proxy from the target-facing socket that match the Client Connection ID can be sent to the client. The proxy MUST use tunnelled mode (HTTP Datagram frames) for any long header packets. The proxy SHOULD forward directly to the client for any matching short header packets if forwarding is supported by the client, but the proxy MAY tunnel these packets in HTTP Datagram frames instead. If the mapping would create a conflict, the proxy responds with a CLOSE_CLIENT_CID capsule.

When the proxy receives a REGISTER_TARGET_CID capsule, it is receiving a request to allow the client to forward packets to the target. If the pair of this Target Connection ID and the client-facing socket on which the request was received does not create a conflict, the proxy creates the mapping and responds with a ACK_TARGET_CID capsule. Once the successful response is sent, the proxy will forward any short header packets received on the client-facing socket that use the Target Connection ID using the correct target-facing socket. If the pair is not unique, the proxy responds with a CLOSE_TARGET_CID capsule. If this occurs, traffic for that Target Connection ID can only use tunnelled mode, not forwarded.

If the proxy does not support forwarded mode, or does not allow forwarded mode for a particular client or authority by policy, it can reject all REGISTER_TARGET_CID requests with CLOSE_TARGET_CID capsule.

The proxy MUST only forward non-tunnelled packets from the client that are QUIC short header packets (based on the Header Form bit) and have mapped Target Connection IDs. Packets sent by the client that are forwarded SHOULD be considered as activity for restarting QUIC's Idle Timeout [[QUIC](#)].

[5.1.](#) Removing Mapping State

For any connection ID for which the proxy has sent an acknowledgement, any mappings for the connection ID last until either endpoint sends a close capsule or the either side of the HTTP stream closes.

A client that no longer wants a given Connection ID to be forwarded by the proxy sends a CLOSE_CLIENT_CID or CLOSE_TARGET_CID capsule.

If a client's connection to the proxy is terminated for any reason, all mappings associated with all requests are removed.

A proxy can close its target-facing socket once all UDP proxying requests mapped to that socket have been removed.

[5.2.](#) Handling Connection Migration

If a proxy supports QUIC connection migration, it needs to ensure that a migration event does not end up sending too many tunnelled or proxied packets on a new path prior to path validation.

Specifically, the proxy MUST limit the number of packets that it will proxy to an unvalidated client address to the size of an initial congestion window. Proxies additionally SHOULD pace the rate at which packets are sent over a new path to avoid creating unintentional congestion on the new path.

[6.](#) Example

Consider a client that is establishing a new QUIC connection through the proxy. It has selected a Client Connection ID of 0x31323334. In order to inform a proxy of the new QUIC Client Connection ID, the client also sends a REGISTER_CLIENT_CID capsule.

The client will also send the initial QUIC packet with the Long Header form in an HTTP datagram.

Client

Server

```
STREAM(44): HEADERS          ----->
  :method = CONNECT
  :protocol = connect-udp
  :scheme = https
  :path = /target.example.com/443/
  :authority = proxy.example.org
  proxy-quic-forwarding = ?1
  capsule-protocol = ?1
```

```
STREAM(44): DATA ----->
  Capsule Type = REGISTER_CLIENT_CID
  Connection ID = 0x31323334
```

```
DATAGRAM ----->
  Quarter Stream ID = 11
  Context ID = 0
  Payload = Encapsulated QUIC initial
```

```
<----- STREAM(44): HEADERS
      :status = 200
      proxy-quic-forwarding = ?1
      capsule-protocol = ?1
```

```
<----- STREAM(44): DATA
      Capsule Type = ACK_CLIENT_CID
      Connection ID = 0x31323334
```

```
/* Wait for target server to respond to UDP packet. */
```

```
<----- DATAGRAM
      Quarter Stream ID = 11
      Context ID = 0
      Payload = Encapsulated QUIC initial
```

Once the client learns which Connection ID has been selected by the target server, it can send a new request to the proxy to establish a mapping for forwarding. In this case, that ID is 0x61626364. The client sends the following capsule:

```
STREAM(44): DATA ----->
  Capsule Type = REGISTER_TARGET_CID
  Connection ID = 0x61626364
```

```
<----- STREAM(44): DATA
          Capsule Type = ACK_TARGET_CID
          Connection ID = 0x61626364
```

Upon receiving an ACK_TARGET_CID capsule, the client starts sending Short Header packets with a Destination Connection ID of 0x61626364 directly to the proxy (not tunnelled), and these are forwarded directly to the target by the proxy. Similarly, Short Header packets from the target with a Destination Connection ID of 0x31323334 are forwarded directly to the client.

[7.](#) Interactions with Load Balancers

Some QUIC servers are accessed using load balancers, as described in [\[QUIC-LB\]](#). These load balancers route packets to servers based on the server's Connection ID. These Connection IDs are generated in a way that can be coordinated between servers and their load balancers.

If a proxy that supports this extension is itself running behind a load balancer, extra complexity arises once clients start using forwarding mode and sending packets to the proxy that have Destination Connection IDs that belong to the target servers, not the proxy. If the load balancer is not aware of these Connection IDs, or the Connection IDs conflict with other Connection IDs used by the load balancer, packets can be routed incorrectly.

QUIC-aware proxies that use forwarding mode generally SHOULD NOT be run behind load balancers; and if they are, they MUST coordinate between the proxy and the load balancer to create mappings for proxied Connection IDs prior to the proxy ACK_CLIENT_CID or ACK_TARGET_CID capsules to clients.

QUIC-aware proxies that do not allow forwarding mode can function unmodified behind QUIC load balancers.

[8.](#) Packet Size Considerations

Since Initial QUIC packets must be at least 1200 bytes in length, the HTTP Datagram frames that are used for a QUIC-aware proxy MUST be able to carry at least 1200 bytes.

Additionally, clients that connect to a proxy for purpose of proxying QUIC SHOULD start their connection with a larger packet size than 1200 bytes, to account for the overhead of tunnelling an Initial QUIC

packet within an HTTP Datagram frame. If the client does not begin with a larger packet size than 1200 bytes, it will need to perform Path MTU (Maximum Transmission Unit) discovery to discover a larger path size prior to sending any tunnelled Initial QUIC packets.

Once a proxied QUIC connections moves into forwarded mode, the client SHOULD initiate Path MTU discovery to increase its end-to-end MTU.

9. Security Considerations

Proxies that support this extension SHOULD provide protections to rate-limit or restrict clients from opening an excessive number of proxied connections, so as to limit abuse or use of proxies to launch Denial-of-Service attacks.

Sending QUIC packets by forwarding through a proxy without tunnelling exposes some QUIC header metadata to onlookers, and can be used to correlate packet flows if an attacker is able to see traffic on both sides of the proxy. Tunnelled packets have similar inference problems. An attacker on both sides of the proxy can use the size of ingress and egress packets to correlate packets belonging to the same connection. (Absent client-side padding, tunneled packets will typically have a fixed amount of overhead that is removed before their HTTP Datagram contents are written to the target.)

Since proxies that forward QUIC packets do not perform any cryptographic integrity check, it is possible that these packets are either malformed, replays, or otherwise malicious. This may result in proxy targets rate limiting or decreasing the reputation of a given proxy.

10. IANA Considerations

10.1. HTTP Header

This document registers the "Proxy-QUIC-Forwarding" header in the "Permanent Message Header Field Names"

<<https://www.iana.org/assignments/message-headers>>.

Header Field Name	Protocol	Status	Reference
Proxy-QUIC-Forwarding	http	exp	This document

Figure 2: Registered HTTP Header

Internet-Draft

QUIC Proxy

March 2022

10.2. Capsule Types

This document registers six new values in the "HTTP Capsule Types" registry established by [HTTP-DGRAM].

Capule Type	Value	Specification
REGISTER_CLIENT_CID	0xffe100	This Document
REGISTER_TARGET_CID	0xffe101	This Document
ACK_CLIENT_CID	0xffe102	This Document
ACK_TARGET_CID	0xffe103	This Document
CLOSE_CLIENT_CID	0xffe104	This Document
CLOSE_TARGET_CID	0xffe105	This Document

Table 1: Registered Capsule Types

11. References

11.1. Normative References

[CONNECT-UDP]

Schinazi, D., "UDP Proxying Support for HTTP", Work in Progress, Internet-Draft, [draft-ietf-masque-connect-udp-07](https://datatracker.ietf.org/doc/html/draft-ietf-masque-connect-udp-07), 4 March 2022, <<https://datatracker.ietf.org/doc/html/draft-ietf-masque-connect-udp-07>>.

[HTTP-DGRAM]

Schinazi, D. and L. Pardue, "Using Datagrams with HTTP", Work in Progress, Internet-Draft, [draft-ietf-masque-h3-datagram-06](https://datatracker.ietf.org/doc/html/draft-ietf-masque-h3-datagram-06), 4 March 2022, <<https://datatracker.ietf.org/doc/html/draft-ietf-masque-h3-datagram-06>>.

[HTTP3] Bishop, M., "Hypertext Transfer Protocol Version 3 (HTTP/3)", Work in Progress, Internet-Draft, [draft-ietf-quic-http-34](https://datatracker.ietf.org/doc/html/draft-ietf-quic-http-34), 2 February 2021, <<https://datatracker.ietf.org/doc/html/draft-ietf-quic-http-34>>.

[INVARIANTS]

Thomson, M., "Version-Independent Properties of QUIC", [RFC 8999](https://www.rfc-editor.org/rfc/rfc8999), DOI 10.17487/RFC8999, May 2021, <<https://www.rfc-editor.org/rfc/rfc8999>>.

[QUIC] Iyengar, J., Ed. and M. Thomson, Ed., "QUIC: A UDP-Based Multiplexed and Secure Transport", [RFC 9000](https://www.rfc-editor.org/rfc/rfc9000), DOI 10.17487/RFC9000, May 2021, <<https://www.rfc-editor.org/rfc/rfc9000>>.

[RFC2119] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", [BCP 14](https://www.rfc-editor.org/rfc/rfc2119), [RFC 2119](https://www.rfc-editor.org/rfc/rfc2119), DOI 10.17487/RFC2119, March 1997, <<https://www.rfc-editor.org/rfc/rfc2119>>.

[RFC8174] Leiba, B., "Ambiguity of Uppercase vs Lowercase in [RFC 2119](https://www.rfc-editor.org/rfc/rfc8174) Key Words", [BCP 14](https://www.rfc-editor.org/rfc/rfc8174), [RFC 8174](https://www.rfc-editor.org/rfc/rfc8174), DOI 10.17487/RFC8174, May 2017, <<https://www.rfc-editor.org/rfc/rfc8174>>.

[RFC8941] Nottingham, M. and P-H. Kamp, "Structured Field Values for HTTP", [RFC 8941](https://www.rfc-editor.org/rfc/rfc8941), DOI 10.17487/RFC8941, February 2021, <<https://www.rfc-editor.org/rfc/rfc8941>>.

[11.2](#). Informative References

[QUIC-LB] Duke, M., Banks, N., and C. Huitema, "QUIC-LB: Generating Routable QUIC Connection IDs", Work in Progress, Internet-Draft, [draft-ietf-quic-load-balancers-12](https://datatracker.ietf.org/doc/html/draft-ietf-quic-load-balancers-12), 11 February 2022, <<https://datatracker.ietf.org/doc/html/draft-ietf-quic-load-balancers-12>>.

Acknowledgments

Thanks to Lucas Pardue, Ryan Hamilton, and Mirja Kuehlewind for their inputs on this document.

Authors' Addresses

Tommy Pauly
Apple Inc.
One Apple Park Way
Cupertino, California 95014,
United States of America
Email: tpauly@apple.com

Pauly & Schinazi

Expires 6 September 2022

[Page 18]

Internet-Draft

QUIC Proxy

March 2022

David Schinazi
Google LLC
1600 Amphitheatre Parkway
Mountain View, California 94043,
United States of America
Email: dschinazi.ietf@gmail.com

