

Network Working Group
Internet-Draft
Obsoletes: [4008](#) (if approved)
Intended status: Standards Track
Expires: December 26, 2015

S. Perreault
Jive Communications
T. Tsou
Huawei Technologies
S. Sivakumar
Cisco Systems
T. Taylor
PT Taylor Consulting
June 24, 2015

Deprecation of MIB Module NAT-MIB (Managed Objects for Network Address Translators (NAT))
draft-perrault-behave-deprecate-nat-mib-v1-04

Abstract

This memo deprecates MIB module NAT-MIB, a portion of the Management Information Base (MIB) previously defined in [RFC 4008](#) for devices implementing Network Address Translator (NAT) function. A companion document defines a new version, NAT-MIB-V2, which responds to deficiencies found in module NAT-MIB and adds new capabilities.

This document obsoletes [RFC 4008](#). All [RFC 4008](#) MIB objects are included in this version unchanged with only the STATUS changed to deprecated, with a non-substantive exception. The exception was to retype internet addresses with a (SIZE (4|16) qualification to get rid of a SMILINT warning.

Status of This Memo

This Internet-Draft is submitted in full conformance with the provisions of [BCP 78](#) and [BCP 79](#).

Internet-Drafts are working documents of the Internet Engineering Task Force (IETF). Note that other groups may also distribute working documents as Internet-Drafts. The list of current Internet-Drafts is at <http://datatracker.ietf.org/drafts/current/>.

Internet-Drafts are draft documents valid for a maximum of six months and may be updated, replaced, or obsoleted by other documents at any time. It is inappropriate to use Internet-Drafts as reference material or to cite them other than as "work in progress."

This Internet-Draft will expire on December 26, 2015.

Copyright Notice

Copyright (c) 2015 IETF Trust and the persons identified as the document authors. All rights reserved.

This document is subject to [BCP 78](#) and the IETF Trust's Legal Provisions Relating to IETF Documents (<http://trustee.ietf.org/license-info>) in effect on the date of publication of this document. Please review these documents carefully, as they describe your rights and restrictions with respect to this document. Code Components extracted from this document must include Simplified BSD License text as described in Section 4.e of the Trust Legal Provisions and are provided without warranty as described in the Simplified BSD License.

Table of Contents

- [1.](#) Introduction [2](#)
- [2.](#) The Internet-Standard Management Framework [3](#)
- [3.](#) Motivation For Deprecating NAT-MIB [3](#)
 - [3.1.](#) Deprecated Features [3](#)
 - [3.2.](#) Desirable New Features [4](#)
- [4.](#) Definitions [4](#)
- [5.](#) Security Considerations [54](#)
- [6.](#) IANA Considerations [54](#)
- [7.](#) References [55](#)
 - [7.1.](#) Normative References [55](#)
 - [7.2.](#) Informative References [56](#)
- Authors' Addresses [56](#)

1. Introduction

This memo deprecates a portion of the Management Information Base (MIB), MIB module NAT-MIB, for devices implementing the Network Address Translator (NAT) function. New implementations are encouraged to base themselves upon the second version of this MIB module, NAT-MIB-V2, defined in [[I-D.ietf-behave-nat-mib-v2](#)]. NAT types and their characteristics are defined in [[RFC2663](#)]. Traditional NAT function, in particular is defined in [[RFC3022](#)]. Neither NAT-MIB nor NAT-MIB-V2 addresses firewall functions and neither can be used for configuring or monitoring them.

[Section 2](#) provides references to the Simple Network Management Protocol (SNMP) management framework, which was used as the basis for the original MIB module definition and its deprecation. [Section 3](#) provides motivation for the deprecation of module NAT-MIB and its replacement by module NAT-MIB-V2. [Section 4](#) has the complete NAT-MIB module definition, with the STATUS of all objects changed to

deprecated. [Section 5](#) describes security considerations relating to NAT-MIB, basically relying on the security considerations in [\[RFC4008\]](#) and [\[I-D.ietf-behave-nat-mib-v2\]](#).

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "NOT RECOMMENDED", "MAY", and "OPTIONAL" in this document are to be interpreted as described in [\[RFC2119\]](#).

2. The Internet-Standard Management Framework

For a detailed overview of the documents that describe the current Internet-Standard Management Framework, please refer to [Section 7 of \[RFC3410\]](#).

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. MIB objects are generally accessed through the Simple Network Management Protocol (SNMP). Objects in the MIB are defined using the mechanisms defined in the Structure of Management Information (SMI). This memo specifies a MIB module that is compliant to the SMIV2, which is described in STD 58, [\[RFC2578\]](#), STD 58, [\[RFC2579\]](#) and STD 58, [\[RFC2580\]](#).

3. Motivation For Deprecating NAT-MIB

This section provides the motivation for deprecating the NAT-MIB module and its replacement by a new version.

3.1. Deprecated Features

All objects defined in [\[RFC4008\]](#) have been marked with "STATUS deprecated" for the following reasons:

Writability: Experience with NAT has shown that implementations vary tremendously. The NAT algorithms and data structures have little in common across devices, and this results in wildly incompatible configuration parameters. Therefore, few implementations were ever able to claim full compliance.

Lesson learned: the MIB should be read-only as much as possible.

Exposing configuration parameters: Even in read-only mode, many configuration parameters were exposed by [\[RFC4008\]](#) (e.g. timeouts). Since implementations vary wildly in their sets of configuration parameters, few implementations could claim even basic compliance.

Lesson learned: the NAT MIB's purpose is not to expose configuration parameters.

Interfaces: Objects from [[RFC4008](#)] tie NAT state with interfaces (e.g. the interface table, the way map entries are grouped by interface). Many NAT implementations either never keep track of the interface or associate a mapping to a set of interfaces. Since interfaces are at the core of [[RFC4008](#)], many NAT devices were unable to have a proper implementation.

Lesson learned: NAT is a logical function that may be independent of interfaces. Do not tie NAT state with interfaces.

NAT service types: [[RFC4008](#)] used four categories of NAT service: basicNat, napt, bidirectionalNat, twiceNat. These are ill-defined and many implementations either use different categories or do not use categories at all.

Lesson learned: do not try to categorize NAT types.

Limited transport protocol set: The set of transport protocols was defined as: other, icmp, udp, tcp. Furthermore, the numeric values corresponding to those labels were arbitrary, without relation to the actual standard protocol numbers. This meant that NAT implementations were limited to those protocols and were unable to expose information about DCCP, SCTP, etc.

Lesson learned: use standard transport protocol numbers.

[3.2.](#) Desirable New Features

A number of desirable new features have been identified that are not present in NAT-MIB. See the latter part of [[I-D.ietf-behave-nat-mib-v2](#)] [Section 2](#).

[4.](#) Definitions

This MIB module IMPORTS objects from [[RFC2578](#)], [[RFC2579](#)], and [[RFC4001](#)].

```
NAT-MIB DEFINITIONS ::= BEGIN
```

```
IMPORTS
```

```
    MODULE-IDENTITY,  
    OBJECT-TYPE,  
    Integer32,  
    Unsigned32,  
    Gauge32,
```


Counter64,
TimeTicks,
mib-2,
NOTIFICATION-TYPE
 FROM SNMPv2-SMI
TEXTUAL-CONVENTION,
StorageType,
RowStatus
 FROM SNMPv2-TC
MODULE-COMPLIANCE,
NOTIFICATION-GROUP,
OBJECT-GROUP
 FROM SNMPv2-CONF
ifIndex,
ifCounterDiscontinuityGroup
 FROM IF-MIB
SnmpAdminString
 FROM SNMP-FRAMEWORK-MIB
InetAddressType,
InetAddress,
InetAddressNumber
 FROM INET-ADDRESS-MIB;

natMIB MODULE-IDENTITY

 LAST-UPDATED "201506240000Z"

-- RFC Ed.: set to publication date

 ORGANIZATION

 "IETF Behavior Engineering for Hindrance Avoidance
 (BEHAVE) Working Group"

 CONTACT-INFO

 "Working Group Email: behave@ietf.org

 Simon Perreault
 Jive Communications
 Quebec, QC
 Canada

 Email: sperreault@jive.com

 Tina Tsou
 Huawei Technologies
 Bantian, Longgang District
 Shenzhen 518129
 PR China

 Email: tina.tsou.zouting@huawei.com

Senthil Sivakumar
 Cisco Systems
 7100-8 Kit Creek Road
 Research Triangle Park, North Carolina 27709
 USA

Phone: +1 919 392 5158
 Email: ssenthil@cisco.com

Tom Taylor
 PT Taylor Consulting
 Ottawa
 Canada

Email: tom.taylor.stds@gmail.com"

DESCRIPTION

"This MIB module defines the generic managed objects for NAT.

Copyright (C) The Internet Society (2015). This version of this MIB module is part of RFC yyyy; see the RFC itself for full legal notices."

-- RFC Ed.: replace yyyy with actual RFC number & remove this note"

REVISION "201506240000Z"

-- RFC Ed.: set to publication date

DESCRIPTION

"Deprecation, published as RFC yyyy."

-- RFC Ed.: replace yyyy with actual RFC number & set date"

REVISION "200503210000Z" -- 21 March 2005

DESCRIPTION

"Initial version, published as [RFC 4008](#)."

::= { mib-2 123 }

natMIBObjects OBJECT IDENTIFIER ::= { natMIB 1 }

NatProtocolType ::= TEXTUAL-CONVENTION

STATUS deprecated

DESCRIPTION

"A list of protocols that support the network address translation. Inclusion of the values is not intended to imply that those protocols need to be supported. Any change in this TEXTUAL-CONVENTION should also be reflected in the definition of NatProtocolMap, which is a BITS representation of this."

SYNTAX INTEGER {

none (1), -- not specified

other (2), -- none of the following


```
        icmp (3),
        udp (4),
        tcp (5)
    }
```

NatProtocolMap ::= TEXTUAL-CONVENTION

STATUS deprecated

DESCRIPTION

"A bitmap of protocol identifiers that support the network address translation. Any change in this TEXTUAL-CONVENTION should also be reflected in the definition of NatProtocolType."

SYNTAX

```
BITS {
    other (0),
    icmp (1),
    udp (2),
    tcp (3)
}
```

NatAddrMapId ::= TEXTUAL-CONVENTION

DISPLAY-HINT "d"

STATUS deprecated

DESCRIPTION

"A unique id that is assigned to each address map by a NAT enabled device."

SYNTAX Unsigned32 (1..4294967295)

NatBindIdOrZero ::= TEXTUAL-CONVENTION

DISPLAY-HINT "d"

STATUS deprecated

DESCRIPTION

"A unique id that is assigned to each bind by a NAT enabled device. The bind id will be zero in the case of a Symmetric NAT."

SYNTAX Unsigned32 (0..4294967295)

NatBindId ::= TEXTUAL-CONVENTION

DISPLAY-HINT "d"

STATUS deprecated

DESCRIPTION

"A unique id that is assigned to each bind by a NAT enabled device."

SYNTAX Unsigned32 (1..4294967295)

NatSessionId ::= TEXTUAL-CONVENTION

DISPLAY-HINT "d"

STATUS deprecated

DESCRIPTION


```

        "A unique id that is assigned to each session by
        a NAT enabled device."
SYNTAX  Unsigned32 (1..4294967295)

NatBindMode ::= TEXTUAL-CONVENTION
    STATUS deprecated
    DESCRIPTION
        "An indication of whether the bind is
        an address bind or an address port bind."
SYNTAX  INTEGER {
        addressBind (1),
        addressPortBind (2)
        }

NatAssociationType ::= TEXTUAL-CONVENTION
    STATUS deprecated
    DESCRIPTION
        "An indication of whether the association is
        static or dynamic."
SYNTAX  INTEGER {
        static (1),
        dynamic (2)
        }

NatTranslationEntity ::= TEXTUAL-CONVENTION
    STATUS deprecated
    DESCRIPTION
        "An indication of a) the direction of a session for
        which an address map entry, address bind or port
        bind is applicable, and b) the entity (source or
        destination) within the session that is subject to
        translation."
SYNTAX  BITS {
        inboundSrcEndPoint (0),
        outboundDstEndPoint(1),
        inboundDstEndPoint (2),
        outboundSrcEndPoint(3)
        }

--
-- Default Values for the Bind and NAT Protocol Timers
--

natDefTimeouts OBJECT IDENTIFIER ::= { natMIBObjects 1 }

natNotifCtrl OBJECT IDENTIFIER ::= { natMIBObjects 2 }
```



```
--
-- Address Bind and Port Bind related NAT configuration
--

natBindDefIdleTimeout OBJECT-TYPE
    SYNTAX      Unsigned32 (0..4294967295)
    UNITS       "seconds"
    MAX-ACCESS  read-write
    STATUS      deprecated
    DESCRIPTION
        "The default Bind (Address Bind or Port Bind) idle
        timeout parameter.

        If the agent is capable of storing non-volatile
        configuration, then the value of this object must be
        restored after a re-initialization of the management
        system."
    DEFVAL { 0 }
    ::= { natDefTimeouts 1 }

--
-- UDP related NAT configuration
--

natUdpDefIdleTimeout OBJECT-TYPE
    SYNTAX      Unsigned32 (1..4294967295)
    UNITS       "seconds"
    MAX-ACCESS  read-write
    STATUS      deprecated
    DESCRIPTION
        "The default UDP idle timeout parameter.

        If the agent is capable of storing non-volatile
        configuration, then the value of this object must be
        restored after a re-initialization of the management
        system."
    DEFVAL { 300 }
    ::= { natDefTimeouts 2 }

--
-- ICMP related NAT configuration
--

natIcmpDefIdleTimeout OBJECT-TYPE
    SYNTAX      Unsigned32 (1..4294967295)
    UNITS       "seconds"
    MAX-ACCESS  read-write
    STATUS      deprecated
```


DESCRIPTION

"The default ICMP idle timeout parameter.

If the agent is capable of storing non-volatile configuration, then the value of this object must be restored after a re-initialization of the management system."

DEFVAL { 300 }

::= { natDefTimeouts 3 }

--

-- Other protocol parameters

--

natOtherDefIdleTimeout OBJECT-TYPE

SYNTAX Unsigned32 (1..4294967295)

UNITS "seconds"

MAX-ACCESS read-write

STATUS deprecated

DESCRIPTION

"The default idle timeout parameter for protocols represented by the value other (2) in NatProtocolType.

If the agent is capable of storing non-volatile configuration, then the value of this object must be restored after a re-initialization of the management system."

DEFVAL { 60 }

::= { natDefTimeouts 4 }

--

-- TCP related NAT Timers

--

natTcpDefIdleTimeout OBJECT-TYPE

SYNTAX Unsigned32 (1..4294967295)

UNITS "seconds"

MAX-ACCESS read-write

STATUS deprecated

DESCRIPTION

"The default time interval that a NAT session for an established TCP connection is allowed to remain valid without any activity on the TCP connection.

If the agent is capable of storing non-volatile configuration, then the value of this object must be restored after a re-initialization of the management


```
        system."  
    DEFVAL { 86400 }  
    ::= { natDefTimeouts 5 }
```

natTcpDefNegTimeout OBJECT-TYPE

```
SYNTAX      Unsigned32 (1..4294967295)  
UNITS       "seconds"  
MAX-ACCESS  read-write  
STATUS      deprecated
```

DESCRIPTION

"The default time interval that a NAT session for a TCP connection that is not in the established state is allowed to remain valid without any activity on the TCP connection.

If the agent is capable of storing non-volatile configuration, then the value of this object must be restored after a re-initialization of the management system."

```
DEFVAL { 60 }  
::= { natDefTimeouts 6 }
```

natNotifThrottlingInterval OBJECT-TYPE

```
SYNTAX      Integer32 (0 | 5..3600)  
UNITS       "seconds"  
MAX-ACCESS  read-write  
STATUS      deprecated
```

DESCRIPTION

"This object controls the generation of the natPacketDiscard notification.

If this object has a value of zero, then no natPacketDiscard notifications will be transmitted by the agent.

If this object has a non-zero value, then the agent must not generate more than one natPacketDiscard 'notification-event' in the indicated period, where a 'notification-event' is the generation of a single notification PDU type to a list of notification destinations. If additional NAT packets are discarded within the throttling period, then notification-events for these changes must be suppressed by the agent until the current throttling period expires.

If natNotifThrottlingInterval notification generation is enabled, the suggested default throttling period is 60 seconds, but generation of the natPacketDiscard

notification should be disabled by default.

If the agent is capable of storing non-volatile configuration, then the value of this object must be restored after a re-initialization of the management system.

The actual transmission of notifications is controlled via the MIB modules in [RFC 3413](#)."

DEFVAL { 0 }

::= { natNotifCtrl 1 }

--

-- The NAT Interface Table

--

natInterfaceTable OBJECT-TYPE

SYNTAX SEQUENCE OF NatInterfaceEntry

MAX-ACCESS not-accessible

STATUS deprecated

DESCRIPTION

"This table specifies the attributes for interfaces on a device supporting NAT function."

::= { natMIBObjects 3 }

natInterfaceEntry OBJECT-TYPE

SYNTAX NatInterfaceEntry

MAX-ACCESS not-accessible

STATUS deprecated

DESCRIPTION

"Each entry in the natInterfaceTable holds a set of parameters for an interface, instantiated by ifIndex. Therefore, the interface index must have been assigned, according to the applicable procedures, before it can be meaningfully used.

Generally, this means that the interface must exist.

When natStorageType is of type nonVolatile, however, this may reflect the configuration for an interface whose ifIndex has been assigned but for which the supporting implementation is not currently present."

INDEX { ifIndex }

::= { natInterfaceTable 1 }

NatInterfaceEntry ::= SEQUENCE {

natInterfaceRealm INTEGER,

natInterfaceServiceType BITS,


```
    natInterfaceInTranslates      Counter64,
    natInterfaceOutTranslates     Counter64,
    natInterfaceDiscards          Counter64,
    natInterfaceStorageType       StorageType,
    natInterfaceRowStatus         RowStatus
}

natInterfaceRealm OBJECT-TYPE
    SYNTAX      INTEGER {
        private (1),
        public (2)
    }
    MAX-ACCESS  read-create
    STATUS      deprecated
    DESCRIPTION
        "This object identifies whether this interface is
        connected to the private or the public realm."
    DEFVAL     { public }
    ::= { natInterfaceEntry 1 }

natInterfaceServiceType OBJECT-TYPE
    SYNTAX      BITS {
        basicNat (0),
        napt (1),
        bidirectionalNat (2),
        twiceNat (3)
    }
    MAX-ACCESS  read-create
    STATUS      deprecated
    DESCRIPTION
        "An indication of the direction in which new sessions
        are permitted and the extent of translation done within
        the IP and transport headers."
    ::= { natInterfaceEntry 2 }

natInterfaceInTranslates OBJECT-TYPE
    SYNTAX      Counter64
    MAX-ACCESS  read-only
    STATUS      deprecated
    DESCRIPTION
        "Number of packets received on this interface that
        were translated.
        Discontinuities in the value of this counter can occur
        at reinitialization of the management system and at
        other times as indicated by the value of
        ifCounterDiscontinuityTime on the relevant interface."
    ::= { natInterfaceEntry 3 }
```


natInterfaceOutTranslates OBJECT-TYPE

SYNTAX Counter64
MAX-ACCESS read-only
STATUS deprecated
DESCRIPTION

"Number of translated packets that were sent out this interface.

Discontinuities in the value of this counter can occur at reinitialization of the management system and at other times as indicated by the value of ifCounterDiscontinuityTime on the relevant interface."

::= { natInterfaceEntry 4 }

natInterfaceDiscards OBJECT-TYPE

SYNTAX Counter64
MAX-ACCESS read-only
STATUS deprecated
DESCRIPTION

"Number of packets that had to be rejected/dropped due to a lack of resources for this interface.

Discontinuities in the value of this counter can occur at reinitialization of the management system and at other times as indicated by the value of ifCounterDiscontinuityTime on the relevant interface."

::= { natInterfaceEntry 5 }

natInterfaceStorageType OBJECT-TYPE

SYNTAX StorageType
MAX-ACCESS read-create
STATUS deprecated
DESCRIPTION

"The storage type for this conceptual row. Conceptual rows having the value 'permanent' need not allow write-access to any columnar objects in the row."

REFERENCE

"Textual Conventions for SMIV2, [Section 2](#)."

DEFVAL { nonVolatile }

::= { natInterfaceEntry 6 }

natInterfaceRowStatus OBJECT-TYPE

SYNTAX RowStatus
MAX-ACCESS read-create
STATUS deprecated
DESCRIPTION

"The status of this conceptual row.

Until instances of all corresponding columns are appropriately configured, the value of the corresponding instance of the natInterfaceRowStatus column is 'notReady'.

In particular, a newly created row cannot be made active until the corresponding instance of natInterfaceServiceType has been set.

None of the objects in this row may be modified while the value of this object is active(1)."

REFERENCE

"Textual Conventions for SMIV2, [Section 2](#)."

```
::= { natInterfaceEntry 7 }
```

```
--
```

```
-- The Address Map Table
```

```
--
```

```
natAddrMapTable OBJECT-TYPE
```

```
    SYNTAX      SEQUENCE OF NatAddrMapEntry
```

```
    MAX-ACCESS  not-accessible
```

```
    STATUS      deprecated
```

```
    DESCRIPTION
```

```
        "This table lists address map parameters for NAT."
```

```
    ::= { natMIBObjects 4 }
```

```
natAddrMapEntry OBJECT-TYPE
```

```
    SYNTAX      NatAddrMapEntry
```

```
    MAX-ACCESS  not-accessible
```

```
    STATUS      deprecated
```

```
    DESCRIPTION
```

```
        "This entry represents an address map to be used for
        NAT and contributes to the dynamic and/or static
        address mapping tables of the NAT device."
```

```
    INDEX      { ifIndex, natAddrMapIndex }
```

```
    ::= { natAddrMapTable 1 }
```

```
NatAddrMapEntry ::= SEQUENCE {
```

```
    natAddrMapIndex
```

```
    NatAddrMapId,
```

```
    natAddrMapName
```

```
    SnmpAdminString,
```

```
    natAddrMapEntryType
```

```
    NatAssociationType,
```

```
    natAddrMapTranslationEntity
```

```
    NatTranslationEntity,
```

```
    natAddrMapLocalAddrType
```

```
    InetAddressType,
```

```
    natAddrMapLocalAddrFrom
```

```
    InetAddress,
```

```
    natAddrMapLocalAddrTo
```

```
    InetAddress,
```

```
    natAddrMapLocalPortFrom
```

```
    InetPortNumber,
```



```

    natAddrMapLocalPortTo      InetPortNumber,
    natAddrMapGlobalAddrType  InetAddressType,
    natAddrMapGlobalAddrFrom  InetAddress,
    natAddrMapGlobalAddrTo    InetAddress,
    natAddrMapGlobalPortFrom  InetPortNumber,
    natAddrMapGlobalPortTo    InetPortNumber,
    natAddrMapProtocol        NatProtocolMap,
    natAddrMapInTranslates    Counter64,
    natAddrMapOutTranslates   Counter64,
    natAddrMapDiscards        Counter64,
    natAddrMapAddrUsed        Gauge32,
    natAddrMapStorageType     StorageType,
    natAddrMapRowStatus        RowStatus
}

```

```

natAddrMapIndex OBJECT-TYPE
    SYNTAX      NatAddrMapId
    MAX-ACCESS  not-accessible
    STATUS      deprecated
    DESCRIPTION
        "Along with ifIndex, this object uniquely
         identifies an entry in the natAddrMapTable.
         Address map entries are applied in the order
         specified by natAddrMapIndex."
    ::= { natAddrMapEntry 1 }

```

```

natAddrMapName OBJECT-TYPE
    SYNTAX      SnmpAdminString (SIZE(1..32))
    MAX-ACCESS  read-create
    STATUS      deprecated
    DESCRIPTION
        "Name identifying all map entries in the table associated
         with the same interface. All map entries with the same
         ifIndex MUST have the same map name."
    ::= { natAddrMapEntry 2 }

```

```

natAddrMapEntryType OBJECT-TYPE
    SYNTAX      NatAssociationType
    MAX-ACCESS  read-create
    STATUS      deprecated
    DESCRIPTION
        "This parameter can be used to set up static
         or dynamic address maps."
    ::= { natAddrMapEntry 3 }

```

```

natAddrMapTranslationEntity OBJECT-TYPE
    SYNTAX      NatTranslationEntity
    MAX-ACCESS  read-create

```


STATUS deprecated

DESCRIPTION

"The end-point entity (source or destination) in inbound or outbound sessions (i.e., first packets) that may be translated by an address map entry.

Session direction (inbound or outbound) is derived from the direction of the first packet of a session traversing a NAT interface. NAT address (and Transport-ID) maps may be defined to effect inbound or outbound sessions.

Traditionally, address maps for Basic NAT and NAPT are configured on a public interface for outbound sessions, effecting translation of source end-point. The value of this object must be set to outboundSrcEndPoint for those interfaces.

Alternately, if address maps for Basic NAT and NAPT were to be configured on a private interface, the desired value for this object for the map entries would be inboundSrcEndPoint (i.e., effecting translation of source end-point for inbound sessions).

If TwiceNAT were to be configured on a private interface, the desired value for this object for the map entries would be a bitmask of inboundSrcEndPoint and inboundDstEndPoint."

::= { natAddrMapEntry 4 }

natAddrMapLocalAddrType OBJECT-TYPE

SYNTAX InetAddressType

MAX-ACCESS read-create

STATUS deprecated

DESCRIPTION

"This object specifies the address type used for natAddrMapLocalAddrFrom and natAddrMapLocalAddrTo."

::= { natAddrMapEntry 5 }

natAddrMapLocalAddrFrom OBJECT-TYPE

SYNTAX InetAddress

MAX-ACCESS read-create

STATUS deprecated

DESCRIPTION

"This object specifies the first IP address of the range of IP addresses mapped by this translation entry. The value of this object must be less than or equal to the value of the natAddrMapLocalAddrTo object.

The type of this address is determined by the value of the natAddrMapLocalAddrType object."
 ::= { natAddrMapEntry 6 }

natAddrMapLocalAddrTo OBJECT-TYPE

SYNTAX InetAddress

MAX-ACCESS read-create

STATUS deprecated

DESCRIPTION

"This object specifies the last IP address of the range of IP addresses mapped by this translation entry. If only a single address is being mapped, the value of this object is equal to the value of natAddrMapLocalAddrFrom. For a static NAT, the number of addresses in the range defined by natAddrMapLocalAddrFrom and natAddrMapLocalAddrTo must be equal to the number of addresses in the range defined by natAddrMapGlobalAddrFrom and natAddrMapGlobalAddrTo. The value of this object must be greater than or equal to the value of the natAddrMapLocalAddrFrom object.

The type of this address is determined by the value of the natAddrMapLocalAddrType object."
 ::= { natAddrMapEntry 7 }

natAddrMapLocalPortFrom OBJECT-TYPE

SYNTAX InetPortNumber

MAX-ACCESS read-create

STATUS deprecated

DESCRIPTION

"If this conceptual row describes a Basic NAT address mapping, then the value of this object must be zero. If this conceptual row describes NAPT, then the value of this object specifies the first port number in the range of ports being mapped.

The value of this object must be less than or equal to the value of the natAddrMapLocalPortTo object. If the translation specifies a single port, then the value of this object is equal to the value of natAddrMapLocalPortTo."

DEFVAL { 0 }

::= { natAddrMapEntry 8 }

natAddrMapLocalPortTo OBJECT-TYPE

SYNTAX InetPortNumber

MAX-ACCESS read-create

STATUS deprecated

DESCRIPTION

"If this conceptual row describes a Basic NAT address mapping, then the value of this object must be zero. If this conceptual row describes NAT, then the value of this object specifies the last port number in the range of ports being mapped.

The value of this object must be greater than or equal to the value of the natAddrMapLocalPortFrom object. If the translation specifies a single port, then the value of this object is equal to the value of natAddrMapLocalPortFrom."

DEFVAL { 0 }

::= { natAddrMapEntry 9 }

natAddrMapGlobalAddrType OBJECT-TYPE

SYNTAX InetAddressType

MAX-ACCESS read-create

STATUS deprecated

DESCRIPTION

"This object specifies the address type used for natAddrMapGlobalAddrFrom and natAddrMapGlobalAddrTo."

::= { natAddrMapEntry 10 }

natAddrMapGlobalAddrFrom OBJECT-TYPE

SYNTAX InetAddress

MAX-ACCESS read-create

STATUS deprecated

DESCRIPTION

"This object specifies the first IP address of the range of IP addresses being mapped to. The value of this object must be less than or equal to the value of the natAddrMapGlobalAddrTo object.

The type of this address is determined by the value of the natAddrMapGlobalAddrType object."

::= { natAddrMapEntry 11 }

natAddrMapGlobalAddrTo OBJECT-TYPE

SYNTAX InetAddress

MAX-ACCESS read-create

STATUS deprecated

DESCRIPTION

"This object specifies the last IP address of the range of IP addresses being mapped to. If only a single address is being mapped to, the value of this object is equal to the value of natAddrMapGlobalAddrFrom. For a static NAT, the number of addresses in the range defined

by natAddrMapGlobalAddrFrom and natAddrMapGlobalAddrTo must be equal to the number of addresses in the range defined by natAddrMapLocalAddrFrom and natAddrMapLocalAddrTo. The value of this object must be greater than or equal to the value of the natAddrMapGlobalAddrFrom object.

The type of this address is determined by the value of the natAddrMapGlobalAddrType object."

```
::= { natAddrMapEntry 12 }
```

natAddrMapGlobalPortFrom OBJECT-TYPE

SYNTAX InetPortNumber

MAX-ACCESS read-create

STATUS deprecated

DESCRIPTION

"If this conceptual row describes a Basic NAT address mapping, then the value of this object must be zero. If this conceptual row describes NAPT, then the value of this object specifies the first port number in the range of ports being mapped to.

The value of this object must be less than or equal to the value of the natAddrMapGlobalPortTo object. If the translation specifies a single port, then the value of this object is equal to the value natAddrMapGlobalPortTo."

```
DEFVAL { 0 }
```

```
::= { natAddrMapEntry 13 }
```

natAddrMapGlobalPortTo OBJECT-TYPE

SYNTAX InetPortNumber

MAX-ACCESS read-create

STATUS deprecated

DESCRIPTION

"If this conceptual row describes a Basic NAT address mapping, then the value of this object must be zero. If this conceptual row describes NAPT, then the value of this object specifies the last port number in the range of ports being mapped to.

The value of this object must be greater than or equal to the value of the natAddrMapGlobalPortFrom object. If the translation specifies a single port, then the value of this object is equal to the value of natAddrMapGlobalPortFrom."

```
DEFVAL { 0 }
```



```
 ::= { natAddrMapEntry 14 }
```

```
natAddrMapProtocol OBJECT-TYPE
```

```
SYNTAX      NatProtocolMap
```

```
MAX-ACCESS  read-create
```

```
STATUS      deprecated
```

```
DESCRIPTION
```

```
    "This object specifies a bitmap of protocol identifiers."
```

```
 ::= { natAddrMapEntry 15 }
```

```
natAddrMapInTranslates OBJECT-TYPE
```

```
SYNTAX      Counter64
```

```
MAX-ACCESS  read-only
```

```
STATUS      deprecated
```

```
DESCRIPTION
```

```
    "The number of inbound packets pertaining to this address  
    map entry that were translated.
```

```
    Discontinuities in the value of this counter can occur  
    at reinitialization of the management system and at  
    other times, as indicated by the value of  
    ifCounterDiscontinuityTime on the relevant interface."
```

```
 ::= { natAddrMapEntry 16 }
```

```
natAddrMapOutTranslates OBJECT-TYPE
```

```
SYNTAX      Counter64
```

```
MAX-ACCESS  read-only
```

```
STATUS      deprecated
```

```
DESCRIPTION
```

```
    "The number of outbound packets pertaining to this  
    address map entry that were translated.
```

```
    Discontinuities in the value of this counter can occur  
    at reinitialization of the management system and at  
    other times, as indicated by the value of  
    ifCounterDiscontinuityTime on the relevant interface."
```

```
 ::= { natAddrMapEntry 17 }
```

```
natAddrMapDiscards OBJECT-TYPE
```

```
SYNTAX      Counter64
```

```
MAX-ACCESS  read-only
```

```
STATUS      deprecated
```

```
DESCRIPTION
```

```
    "The number of packets pertaining to this address map  
    entry that were dropped due to lack of addresses in the  
    address pool identified by this address map. The value  
    of this object must always be zero in case of static  
    address map.
```


Discontinuities in the value of this counter can occur at reinitialization of the management system and at other times, as indicated by the value of ifCounterDiscontinuityTime on the relevant interface."

::= { natAddrMapEntry 18 }

natAddrMapAddrUsed OBJECT-TYPE

SYNTAX Gauge32

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"The number of addresses pertaining to this address map that are currently being used from the NAT pool. The value of this object must always be zero in the case of a static address map."

::= { natAddrMapEntry 19 }

natAddrMapStorageType OBJECT-TYPE

SYNTAX StorageType

MAX-ACCESS read-create

STATUS deprecated

DESCRIPTION

"The storage type for this conceptual row. Conceptual rows having the value 'permanent' need not allow write-access to any columnar objects in the row."

REFERENCE

"Textual Conventions for SMIV2, [Section 2](#)."

DEFVAL { nonVolatile }

::= { natAddrMapEntry 20 }

natAddrMapRowStatus OBJECT-TYPE

SYNTAX RowStatus

MAX-ACCESS read-create

STATUS deprecated

DESCRIPTION

"The status of this conceptual row.

Until instances of all corresponding columns are appropriately configured, the value of the corresponding instance of the natAddrMapRowStatus column is 'notReady'.

None of the objects in this row may be modified while the value of this object is active(1)."

REFERENCE

"Textual Conventions for SMIV2, [Section 2](#)."

::= { natAddrMapEntry 21 }


```
--
-- Address Bind section
--

natAddrBindNumberOfEntries OBJECT-TYPE
    SYNTAX      Gauge32
    MAX-ACCESS  read-only
    STATUS      deprecated
    DESCRIPTION
        "This object maintains a count of the number of entries
         that currently exist in the natAddrBindTable."
    ::= { natMIBObjects 5 }

--
-- The NAT Address BIND Table
--

natAddrBindTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF NatAddrBindEntry
    MAX-ACCESS  not-accessible
    STATUS      deprecated
    DESCRIPTION
        "This table holds information about the currently
         active NAT BINDs."
    ::= { natMIBObjects 6 }

natAddrBindEntry OBJECT-TYPE
    SYNTAX      NatAddrBindEntry
    MAX-ACCESS  not-accessible
    STATUS      deprecated
    DESCRIPTION
        "Each entry in this table holds information about
         an active address BIND.  These entries are lost
         upon agent restart.

         This row has indexing which may create variables with
         more than 128 subidentifiers.  Implementers of this
         table must be careful not to create entries that would
         result in OIDs which exceed the 128 subidentifier limit.
         Otherwise, the information cannot be accessed using
         SNMPv1, SNMPv2c or SNMPv3."

    INDEX      { ifIndex,
                 natAddrBindLocalAddrType,
                 natAddrBindLocalAddr }
    ::= { natAddrBindTable 1 }

NatAddrBindEntry ::= SEQUENCE {
```



```

    natAddrBindLocalAddrType      InetAddressType,
    natAddrBindLocalAddr          InetAddress,
    natAddrBindGlobalAddrType     InetAddressType,
    natAddrBindGlobalAddr        InetAddress,
    natAddrBindId                 NatBindId,
    natAddrBindTranslationEntity   NatTranslationEntity,
    natAddrBindType               NatAssociationType,
    natAddrBindMapIndex           NatAddrMapId,
    natAddrBindSessions           Gauge32,
    natAddrBindMaxIdleTime        TimeTicks,
    natAddrBindCurrentIdleTime    TimeTicks,
    natAddrBindInTranslates       Counter64,
    natAddrBindOutTranslates      Counter64
}

```

natAddrBindLocalAddrType OBJECT-TYPE

```

SYNTAX      InetAddressType
MAX-ACCESS  not-accessible
STATUS      deprecated
DESCRIPTION
    "This object specifies the address type used for
    natAddrBindLocalAddr."
 ::= { natAddrBindEntry 1 }

```

natAddrBindLocalAddr OBJECT-TYPE

```

SYNTAX      InetAddress (SIZE (4|16))
MAX-ACCESS  not-accessible
STATUS      deprecated
DESCRIPTION
    "This object represents the private-realm specific
    network layer address, which maps to the public-realm
    address represented by natAddrBindGlobalAddr.

    The type of this address is determined by the value of
    the natAddrBindLocalAddrType object."
 ::= { natAddrBindEntry 2 }

```

natAddrBindGlobalAddrType OBJECT-TYPE

```

SYNTAX      InetAddressType
MAX-ACCESS  read-only
STATUS      deprecated
DESCRIPTION
    "This object specifies the address type used for
    natAddrBindGlobalAddr."
 ::= { natAddrBindEntry 3 }

```

natAddrBindGlobalAddr OBJECT-TYPE

```

SYNTAX      InetAddress

```


MAX-ACCESS read-only
STATUS deprecated
DESCRIPTION

"This object represents the public-realm network layer address that maps to the private-realm network layer address represented by natAddrBindLocalAddr.

The type of this address is determined by the value of the natAddrBindGlobalAddrType object."

::= { natAddrBindEntry 4 }

natAddrBindId OBJECT-TYPE

SYNTAX NatBindId
MAX-ACCESS read-only
STATUS deprecated
DESCRIPTION

"This object represents a bind id that is dynamically assigned to each bind by a NAT enabled device. Each bind is represented by a bind id that is unique across both, the natAddrBindTable and the natAddrPortBindTable."

::= { natAddrBindEntry 5 }

natAddrBindTranslationEntity OBJECT-TYPE

SYNTAX NatTranslationEntity
MAX-ACCESS read-only
STATUS deprecated
DESCRIPTION

"This object represents the direction of sessions for which this bind is applicable and the endpoint entity (source or destination) within the sessions that is subject to translation using the BIND.

Orientation of the bind can be a superset of translationEntity of the address map entry which forms the basis for this bind.

For example, if the translationEntity of an address map entry is outboundSrcEndPoint, the translationEntity of a bind derived from this map entry may either be outboundSrcEndPoint or it may be bidirectional (a bitmask of outboundSrcEndPoint and inboundDstEndPoint)."

::= { natAddrBindEntry 6 }

natAddrBindType OBJECT-TYPE

SYNTAX NatAssociationType
MAX-ACCESS read-only

STATUS deprecated
DESCRIPTION
"This object indicates whether the bind is static or dynamic."
::= { natAddrBindEntry 7 }

natAddrBindMapIndex OBJECT-TYPE

SYNTAX NatAddrMapId
MAX-ACCESS read-only
STATUS deprecated
DESCRIPTION
"This object is a pointer to the natAddrMapTable entry (and the parameters of that entry) which was used in creating this BIND. This object, in conjunction with the ifIndex (which identifies a unique addrMapName) points to a unique entry in the natAddrMapTable."
::= { natAddrBindEntry 8 }

natAddrBindSessions OBJECT-TYPE

SYNTAX Gauge32
MAX-ACCESS read-only
STATUS deprecated
DESCRIPTION
"Number of sessions currently using this BIND."
::= { natAddrBindEntry 9 }

natAddrBindMaxIdleTime OBJECT-TYPE

SYNTAX TimeTicks
MAX-ACCESS read-only
STATUS deprecated
DESCRIPTION
"This object indicates the maximum time for which this bind can be idle with no sessions attached to it.

The value of this object is of relevance only for dynamic NAT."
::= { natAddrBindEntry 10 }

natAddrBindCurrentIdleTime OBJECT-TYPE

SYNTAX TimeTicks
MAX-ACCESS read-only
STATUS deprecated
DESCRIPTION
"At any given instance, this object indicates the time that this bind has been idle without any sessions attached to it."

The value of this object is of relevance only for dynamic NAT."
 ::= { natAddrBindEntry 11 }

natAddrBindInTranslates OBJECT-TYPE

SYNTAX Counter64

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"The number of inbound packets that were successfully translated by using this bind entry.

Discontinuities in the value of this counter can occur at reinitialization of the management system and at other times, as indicated by the value of ifCounterDiscontinuityTime on the relevant interface."

::= { natAddrBindEntry 12 }

natAddrBindOutTranslates OBJECT-TYPE

SYNTAX Counter64

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"The number of outbound packets that were successfully translated using this bind entry.

Discontinuities in the value of this counter can occur at reinitialization of the management system and at other times as indicated by the value of ifCounterDiscontinuityTime on the relevant interface."

::= { natAddrBindEntry 13 }

--
-- Address Port Bind section
--

natAddrPortBindNumberOfEntries OBJECT-TYPE

SYNTAX Gauge32

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"This object maintains a count of the number of entries that currently exist in the natAddrPortBindTable."

::= { natMIBObjects 7 }

--
-- The NAT Address Port Bind Table
--

natAddrPortBindTable OBJECT-TYPE

SYNTAX SEQUENCE OF NatAddrPortBindEntry

MAX-ACCESS not-accessible

STATUS deprecated

DESCRIPTION

"This table holds information about the currently active NAPT BINDs."

::= { natMIBObjects 8 }

natAddrPortBindEntry OBJECT-TYPE

SYNTAX NatAddrPortBindEntry

MAX-ACCESS not-accessible

STATUS deprecated

DESCRIPTION

"Each entry in the this table holds information about a NAPT bind that is currently active. These entries are lost upon agent restart."

This row has indexing which may create variables with more than 128 subidentifiers. Implementers of this table must be careful not to create entries which would result in OIDs that exceed the 128 subidentifier limit. Otherwise, the information cannot be accessed using SNMPv1, SNMPv2c or SNMPv3."

INDEX { ifIndex, natAddrPortBindLocalAddrType, natAddrPortBindLocalAddr, natAddrPortBindLocalPort, natAddrPortBindProtocol }

::= { natAddrPortBindTable 1 }

NatAddrPortBindEntry ::= SEQUENCE {

natAddrPortBindLocalAddrType InetAddressType,

natAddrPortBindLocalAddr InetAddress,

natAddrPortBindLocalPort InetPortNumber,

natAddrPortBindProtocol NatProtocolType,

natAddrPortBindGlobalAddrType InetAddressType,

natAddrPortBindGlobalAddr InetAddress,

natAddrPortBindGlobalPort InetPortNumber,

natAddrPortBindId NatBindId,

natAddrPortBindTranslationEntity NatTranslationEntity,

natAddrPortBindType NatAssociationType,

natAddrPortBindMapIndex NatAddrMapId,

natAddrPortBindSessions Gauge32,

natAddrPortBindMaxIdleTime TimeTicks,

natAddrPortBindCurrentIdleTime TimeTicks,

natAddrPortBindInTranslates Counter64,

natAddrPortBindOutTranslates Counter64

}

natAddrPortBindLocalAddrType OBJECT-TYPE

SYNTAX InetAddressType

MAX-ACCESS not-accessible

STATUS deprecated

DESCRIPTION

"This object specifies the address type used for natAddrPortBindLocalAddr."

::= { natAddrPortBindEntry 1 }

natAddrPortBindLocalAddr OBJECT-TYPE

SYNTAX InetAddress (SIZE(4|16))

MAX-ACCESS not-accessible

STATUS deprecated

DESCRIPTION

"This object represents the private-realm specific network layer address which, in conjunction with natAddrPortBindLocalPort, maps to the public-realm network layer address and transport id represented by natAddrPortBindGlobalAddr and natAddrPortBindGlobalPort respectively.

The type of this address is determined by the value of the natAddrPortBindLocalAddrType object."

::= { natAddrPortBindEntry 2 }

natAddrPortBindLocalPort OBJECT-TYPE

SYNTAX InetPortNumber

MAX-ACCESS not-accessible

STATUS deprecated

DESCRIPTION

"For a protocol value TCP or UDP, this object represents the private-realm specific port number. On the other hand, for ICMP a bind is created only for query/response type ICMP messages such as ICMP echo, Timestamp, and Information request messages, and this object represents the private-realm specific identifier in the ICMP message, as defined in [RFC 792](#) for ICMPv4 and in [RFC 2463](#) for ICMPv6.

This object, together with natAddrPortBindProtocol, natAddrPortBindLocalAddrType, and natAddrPortBindLocalAddr, constitutes a session endpoint in the private realm. A bind entry binds a private realm specific endpoint to a public realm specific endpoint, as represented by the tuple of (natAddrPortBindGlobalPort, natAddrPortBindProtocol, natAddrPortBindGlobalAddrType, and


```
        natAddrPortBindGlobalAddr)."
 ::= { natAddrPortBindEntry 3 }
```

natAddrPortBindProtocol OBJECT-TYPE

```
SYNTAX      NatProtocolType
MAX-ACCESS  not-accessible
STATUS      deprecated
DESCRIPTION
```

```
"This object specifies a protocol identifier.  If the
value of this object is none(1), then this bind entry
applies to all IP traffic.  Any other value of this
object specifies the class of IP traffic to which this
BIND applies."
```

```
 ::= { natAddrPortBindEntry 4 }
```

natAddrPortBindGlobalAddrType OBJECT-TYPE

```
SYNTAX      InetAddressType
MAX-ACCESS  read-only
STATUS      deprecated
DESCRIPTION
```

```
"This object specifies the address type used for
natAddrPortBindGlobalAddr."
```

```
 ::= { natAddrPortBindEntry 5 }
```

natAddrPortBindGlobalAddr OBJECT-TYPE

```
SYNTAX      InetAddress
MAX-ACCESS  read-only
STATUS      deprecated
DESCRIPTION
```

```
"This object represents the public-realm specific network
layer address that, in conjunction with
natAddrPortBindGlobalPort, maps to the private-realm
```

```
network layer address and transport id represented by
natAddrPortBindLocalAddr and natAddrPortBindLocalPort,
respectively.
```

```
The type of this address is determined by the value of
the natAddrPortBindGlobalAddrType object."
```

```
 ::= { natAddrPortBindEntry 6 }
```

natAddrPortBindGlobalPort OBJECT-TYPE

```
SYNTAX      InetPortNumber
MAX-ACCESS  read-only
STATUS      deprecated
DESCRIPTION
```

```
"For a protocol value TCP or UDP, this object represents
the public-realm specific port number.  On the other
```


hand, for ICMP a bind is created only for query/response type ICMP messages such as ICMP echo, Timestamp, and Information request messages, and this object represents the public-realm specific identifier in the ICMP message, as defined in [RFC 792](#) for ICMPv4 and in [RFC 2463](#) for ICMPv6.

This object, together with natAddrPortBindProtocol, natAddrPortBindGlobalAddrType, and natAddrPortBindGlobalAddr, constitutes a session endpoint in the public realm. A bind entry binds a public realm specific endpoint to a private realm specific endpoint, as represented by the tuple of (natAddrPortBindLocalPort, natAddrPortBindProtocol, natAddrPortBindLocalAddrType, and natAddrPortBindLocalAddr)."

```
::= { natAddrPortBindEntry 7 }
```

natAddrPortBindId OBJECT-TYPE

```
SYNTAX      NatBindId
MAX-ACCESS  read-only
STATUS      deprecated
DESCRIPTION
```

"This object represents a bind id that is dynamically assigned to each bind by a NAT enabled device. Each bind is represented by a unique bind id across both the natAddrBindTable and the natAddrPortBindTable."

```
::= { natAddrPortBindEntry 8 }
```

natAddrPortBindTranslationEntity OBJECT-TYPE

```
SYNTAX      NatTranslationEntity
MAX-ACCESS  read-only
STATUS      deprecated
DESCRIPTION
```

"This object represents the direction of sessions for which this bind is applicable and the entity (source or destination) within the sessions that is subject to translation with the BIND.

Orientation of the bind can be a superset of the translationEntity of the address map entry that forms the basis for this bind.

For example, if the translationEntity of an address map entry is outboundSrcEndPoint, the translationEntity of a bind derived from this map entry may either be outboundSrcEndPoint or may be bidirectional (a bitmask of


```
        outboundSrcEndPoint and inboundDstEndPoint)."  
 ::= { natAddrPortBindEntry 9 }
```

natAddrPortBindType OBJECT-TYPE

SYNTAX NatAssociationType

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"This object indicates whether the bind is static or
dynamic."

```
 ::= { natAddrPortBindEntry 10 }
```

natAddrPortBindMapIndex OBJECT-TYPE

SYNTAX NatAddrMapId

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"This object is a pointer to the natAddrMapTable entry
(and the parameters of that entry) used in
creating this BIND. This object, in conjunction with
the ifIndex (which identifies a unique addrMapName),
points to a unique entry in the natAddrMapTable."

```
 ::= { natAddrPortBindEntry 11 }
```

natAddrPortBindSessions OBJECT-TYPE

SYNTAX Gauge32

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"Number of sessions currently using this BIND."

```
 ::= { natAddrPortBindEntry 12 }
```

natAddrPortBindMaxIdleTime OBJECT-TYPE

SYNTAX TimeTicks

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"This object indicates the maximum time for
which this bind can be idle without any sessions
attached to it.

The value of this object is of relevance
only for dynamic NAT."

```
 ::= { natAddrPortBindEntry 13 }
```

natAddrPortBindCurrentIdleTime OBJECT-TYPE

SYNTAX TimeTicks

MAX-ACCESS read-only

STATUS deprecated
DESCRIPTION
"At any given instance, this object indicates the time that this bind has been idle without any sessions attached to it.

The value of this object is of relevance only for dynamic NAT."
::= { natAddrPortBindEntry 14 }

natAddrPortBindInTranslates OBJECT-TYPE

SYNTAX Counter64
MAX-ACCESS read-only
STATUS deprecated
DESCRIPTION
"The number of inbound packets that were translated as per this bind entry.

Discontinuities in the value of this counter can occur at reinitialization of the management system and at other times, as indicated by the value of ifCounterDiscontinuityTime on the relevant interface."
::= { natAddrPortBindEntry 15 }

natAddrPortBindOutTranslates OBJECT-TYPE

SYNTAX Counter64
MAX-ACCESS read-only
STATUS deprecated
DESCRIPTION
"The number of outbound packets that were translated as per this bind entry.

Discontinuities in the value of this counter can occur at reinitialization of the management system and at other times, as indicated by the value of ifCounterDiscontinuityTime on the relevant interface."
::= { natAddrPortBindEntry 16 }

--
-- The Session Table
--

natSessionTable OBJECT-TYPE

SYNTAX SEQUENCE OF NatSessionEntry
MAX-ACCESS not-accessible
STATUS deprecated
DESCRIPTION
"The (conceptual) table containing one entry for each

NAT session currently active on this NAT device."
 ::= { natMIBObjects 9 }

natSessionEntry OBJECT-TYPE

SYNTAX NatSessionEntry

MAX-ACCESS not-accessible

STATUS deprecated

DESCRIPTION

"An entry (conceptual row) containing information
 about an active NAT session on this NAT device.

These entries are lost upon agent restart."

INDEX { ifIndex, natSessionIndex }

::= { natSessionTable 1 }

NatSessionEntry ::= SEQUENCE {

natSessionIndex	NatSessionId,
natSessionPrivateSrcEPBindId	NatBindIdOrZero,
natSessionPrivateSrcEPBindMode	NatBindMode,
natSessionPrivateDstEPBindId	NatBindIdOrZero,
natSessionPrivateDstEPBindMode	NatBindMode,
natSessionDirection	INTEGER,
natSessionUpTime	TimeTicks,
natSessionAddrMapIndex	NatAddrMapId,
natSessionProtocolType	NatProtocolType,
natSessionPrivateAddrType	InetAddressType,
natSessionPrivateSrcAddr	InetAddress,
natSessionPrivateSrcPort	InetPortNumber,
natSessionPrivateDstAddr	InetAddress,
natSessionPrivateDstPort	InetPortNumber,
natSessionPublicAddrType	InetAddressType,
natSessionPublicSrcAddr	InetAddress,
natSessionPublicSrcPort	InetPortNumber,
natSessionPublicDstAddr	InetAddress,
natSessionPublicDstPort	InetPortNumber,
natSessionMaxIdleTime	TimeTicks,
natSessionCurrentIdleTime	TimeTicks,
natSessionInTranslates	Counter64,
natSessionOutTranslates	Counter64

}

natSessionIndex OBJECT-TYPE

SYNTAX NatSessionId

MAX-ACCESS not-accessible

STATUS deprecated

DESCRIPTION

"The session ID for this NAT session."

::= { natSessionEntry 1 }

natSessionPrivateSrcEPBindId OBJECT-TYPE

SYNTAX NatBindIdOrZero

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"The bind id associated between private and public source end points. In the case of Symmetric-NAT, this should be set to zero."

::= { natSessionEntry 2 }

natSessionPrivateSrcEPBindMode OBJECT-TYPE

SYNTAX NatBindMode

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"This object indicates whether the bind indicated by the object natSessionPrivateSrcEPBindId is an address bind or an address port bind."

::= { natSessionEntry 3 }

natSessionPrivateDstEPBindId OBJECT-TYPE

SYNTAX NatBindIdOrZero

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"The bind id associated between private and public destination end points."

::= { natSessionEntry 4 }

natSessionPrivateDstEPBindMode OBJECT-TYPE

SYNTAX NatBindMode

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"This object indicates whether the bind indicated by the object natSessionPrivateDstEPBindId is an address bind or an address port bind."

::= { natSessionEntry 5 }

natSessionDirection OBJECT-TYPE

SYNTAX INTEGER {
 inbound (1),
 outbound (2)
}

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"The direction of this session with respect to the local network. 'inbound' indicates that this session was initiated from the public network into the private network. 'outbound' indicates that this session was initiated from the private network into the public network."

::= { natSessionEntry 6 }

natSessionUpTime OBJECT-TYPE

SYNTAX TimeTicks

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"The up time of this session in one-hundredths of a second."

::= { natSessionEntry 7 }

natSessionAddrMapIndex OBJECT-TYPE

SYNTAX NatAddrMapId

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"This object is a pointer to the natAddrMapTable entry (and the parameters of that entry) used in creating this session. This object, in conjunction with the ifIndex (which identifies a unique addrMapName), points to a unique entry in the natAddrMapTable."

::= { natSessionEntry 8 }

natSessionProtocolType OBJECT-TYPE

SYNTAX NatProtocolType

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"The protocol type of this session."

::= { natSessionEntry 9 }

natSessionPrivateAddrType OBJECT-TYPE

SYNTAX InetAddressType

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"This object specifies the address type used for natSessionPrivateSrcAddr and natSessionPrivateDstAddr."

::= { natSessionEntry 10 }

natSessionPrivateSrcAddr OBJECT-TYPE

SYNTAX InetAddress

MAX-ACCESS read-only
STATUS deprecated
DESCRIPTION

"The source IP address of the session endpoint that lies in the private network.

The value of this object must be zero only when the natSessionPrivateSrcEPBindId object has a zero value. When the value of this object is zero, the NAT session lookup will match any IP address to this field.

The type of this address is determined by the value of the natSessionPrivateAddrType object."

::= { natSessionEntry 11 }

natSessionPrivateSrcPort OBJECT-TYPE

SYNTAX InetPortNumber
MAX-ACCESS read-only
STATUS deprecated
DESCRIPTION

"When the value of protocol is TCP or UDP, this object represents the source port in the first packet of session while in private-realm. On the other hand, when the protocol is ICMP, a NAT session is created only for query/response type ICMP messages such as ICMP echo, Timestamp, and Information request messages, and this object represents the private-realm specific identifier in the ICMP message, as defined in [RFC 792](#) for ICMPv4 and in [RFC 2463](#) for ICMPv6.

The value of this object must be zero when the natSessionPrivateSrcEPBindId object has zero value and value of natSessionPrivateSrcEPBindMode is addressPortBind(2). In such a case, the NAT session lookup will match any port number to this field.

The value of this object must be zero when the object is not a representative field (SrcPort, DstPort, or ICMP identifier) of the session tuple in either the public realm or the private realm."

::= { natSessionEntry 12 }

natSessionPrivateDstAddr OBJECT-TYPE

SYNTAX InetAddress
MAX-ACCESS read-only
STATUS deprecated
DESCRIPTION

"The destination IP address of the session endpoint that

lies in the private network.

The value of this object must be zero when the natSessionPrivateDstEPBindId object has a zero value. In such a scenario, the NAT session lookup will match any IP address to this field.

The type of this address is determined by the value of the natSessionPrivateAddrType object."

```
::= { natSessionEntry 13 }
```

natSessionPrivateDstPort OBJECT-TYPE

SYNTAX InetPortNumber

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"When the value of protocol is TCP or UDP, this object represents the destination port in the first packet of session while in private-realm. On the other hand, when the protocol is ICMP, this object is not relevant and should be set to zero.

The value of this object must be zero when the natSessionPrivateDstEPBindId object has a zero value and natSessionPrivateDstEPBindMode is set to addressPortBind(2). In such a case, the NAT session lookup will match any port number to this field.

The value of this object must be zero when the object is not a representative field (SrcPort, DstPort, or ICMP identifier) of the session tuple in either the public realm or the private realm."

```
::= { natSessionEntry 14 }
```

natSessionPublicAddrType OBJECT-TYPE

SYNTAX InetAddressType

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"This object specifies the address type used for natSessionPublicSrcAddr and natSessionPublicDstAddr."

```
::= { natSessionEntry 15 }
```

natSessionPublicSrcAddr OBJECT-TYPE

SYNTAX InetAddress

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"The source IP address of the session endpoint that lies in the public network.

The value of this object must be zero when the natSessionPrivateSrcEPBindId object has a zero value. In such a scenario, the NAT session lookup will match any IP address to this field.

The type of this address is determined by the value of the natSessionPublicAddrType object."

::= { natSessionEntry 16 }

natSessionPublicSrcPort OBJECT-TYPE

SYNTAX InetPortNumber

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"When the value of protocol is TCP or UDP, this object represents the source port in the first packet of session while in public-realm. On the other hand, when protocol is ICMP, a NAT session is created only for query/response type ICMP messages such as ICMP echo, Timestamp, and Information request messages, and this object represents the public-realm specific identifier in the ICMP message, as defined in [RFC 792](#) for ICMPv4 and in [RFC 2463](#) for ICMPv6.

The value of this object must be zero when the natSessionPrivateSrcEPBindId object has a zero value and natSessionPrivateSrcEPBindMode is set to addressPortBind(2). In such a scenario, the NAT session lookup will match any port number to this field.

The value of this object must be zero when the object is not a representative field (SrcPort, DstPort or ICMP identifier) of the session tuple in either the public realm or the private realm."

::= { natSessionEntry 17 }

natSessionPublicDstAddr OBJECT-TYPE

SYNTAX InetAddress

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"The destination IP address of the session endpoint that lies in the public network.

The value of this object must be non-zero when the natSessionPrivateDstEPBindId object has a non-zero value. If the value of this object and the corresponding natSessionPrivateDstEPBindId object value is zero, then the NAT session lookup will match any IP address to this field.

The type of this address is determined by the value of the natSessionPublicAddrType object."

```
::= { natSessionEntry 18 }
```

natSessionPublicDstPort OBJECT-TYPE

SYNTAX InetPortNumber

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"When the value of protocol is TCP or UDP, this object represents the destination port in the first packet of session while in public-realm. On the other hand, when the protocol is ICMP, this object is not relevant for translation and should be zero.

The value of this object must be zero when the natSessionPrivateDstEPBindId object has a zero value and natSessionPrivateDstEPBindMode is addressPortBind(2). In such a scenario, the NAT session lookup will match any port number to this field.

The value of this object must be zero when the object is not a representative field (SrcPort, DstPort, or ICMP identifier) of the session tuple in either the public realm or the private realm."

```
::= { natSessionEntry 19 }
```

natSessionMaxIdleTime OBJECT-TYPE

SYNTAX TimeTicks

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"The max time for which this session can be idle without detecting a packet."

```
::= { natSessionEntry 20 }
```

natSessionCurrentIdleTime OBJECT-TYPE

SYNTAX TimeTicks

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"The time since a packet belonging to this session was last detected."

::= { natSessionEntry 21 }

natSessionInTranslates OBJECT-TYPE

SYNTAX Counter64

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"The number of inbound packets that were translated for this session.

Discontinuities in the value of this counter can occur at reinitialization of the management system and at other times, as indicated by the value of ifCounterDiscontinuityTime on the relevant interface."

::= { natSessionEntry 22 }

natSessionOutTranslates OBJECT-TYPE

SYNTAX Counter64

MAX-ACCESS read-only

STATUS deprecated

DESCRIPTION

"The number of outbound packets that were translated for this session.

Discontinuities in the value of this counter can occur at reinitialization of the management system and at other times, as indicated by the value of ifCounterDiscontinuityTime on the relevant interface."

::= { natSessionEntry 23 }

--

-- The Protocol table

--

natProtocolTable OBJECT-TYPE

SYNTAX SEQUENCE OF NatProtocolEntry

MAX-ACCESS not-accessible

STATUS deprecated

DESCRIPTION

"The (conceptual) table containing per protocol NAT statistics."

::= { natMIBObjects 10 }

natProtocolEntry OBJECT-TYPE

SYNTAX NatProtocolEntry


```
MAX-ACCESS not-accessible
STATUS deprecated
DESCRIPTION
    "An entry (conceptual row) containing NAT statistics
    pertaining to a particular protocol."
INDEX { natProtocol }
 ::= { natProtocolTable 1 }

NatProtocolEntry ::= SEQUENCE {
    natProtocol          NatProtocolType,
    natProtocolInTranslates Counter64,
    natProtocolOutTranslates Counter64,
    natProtocolDiscards Counter64
}

natProtocol OBJECT-TYPE
    SYNTAX NatProtocolType
    MAX-ACCESS not-accessible
    STATUS deprecated
    DESCRIPTION
        "This object represents the protocol pertaining to which
        parameters are reported."
    ::= { natProtocolEntry 1 }

natProtocolInTranslates OBJECT-TYPE
    SYNTAX Counter64
    MAX-ACCESS read-only
    STATUS deprecated
    DESCRIPTION
        "The number of inbound packets pertaining to the protocol
        identified by natProtocol that underwent NAT.

        Discontinuities in the value of this counter can occur
        at reinitialization of the management system and at
        other times, as indicated by the value of
        ifCounterDiscontinuityTime on the relevant interface."
    ::= { natProtocolEntry 2 }

natProtocolOutTranslates OBJECT-TYPE
    SYNTAX Counter64
    MAX-ACCESS read-only
    STATUS deprecated
    DESCRIPTION
        "The number of outbound packets pertaining to the
        protocol identified by natProtocol that underwent NAT.

        Discontinuities in the value of this counter can occur
        at reinitialization of the management system and at
```



```
        other times, as indicated by the value of
        ifCounterDiscontinuityTime on the relevant interface."
 ::= { natProtocolEntry 3 }

natProtocolDiscards OBJECT-TYPE
    SYNTAX      Counter64
    MAX-ACCESS  read-only
    STATUS      deprecated
    DESCRIPTION
        "The number of packets pertaining to the protocol
        identified by natProtocol that had to be
        rejected/dropped due to lack of resources.  These
        rejections could be due to session timeout, resource
        unavailability, lack of address space, etc.

        Discontinuities in the value of this counter can occur
        at reinitialization of the management system and at
        other times, as indicated by the value of
        ifCounterDiscontinuityTime on the relevant interface."
 ::= { natProtocolEntry 4 }

--
-- Notifications section
--

natMIBNotifications OBJECT IDENTIFIER ::= { natMIB 0 }

--
-- Notifications
--

natPacketDiscard NOTIFICATION-TYPE
    OBJECTS { ifIndex }
    STATUS  deprecated
    DESCRIPTION
        "This notification is generated when IP packets are
        discarded by the NAT function; e.g., due to lack of
        mapping space when NAT is out of addresses or ports.

        Note that the generation of natPacketDiscard
        notifications is throttled by the agent, as specified
        by the 'natNotifThrottlingInterval' object."
 ::= { natMIBNotifications 1 }

--
-- Conformance information.
```


--

natMIBConformance OBJECT IDENTIFIER ::= { natMIB 2 }

natMIBGroups OBJECT IDENTIFIER ::= { natMIBConformance 1 }

natMIBCompliances OBJECT IDENTIFIER ::= { natMIBConformance 2 }

--

-- Units of conformance

--

natConfigGroup OBJECT-GROUP

OBJECTS { natInterfaceRealm,
natInterfaceServiceType,
natInterfaceStorageType,
natInterfaceRowStatus,
natAddrMapName,
natAddrMapEntryType,
natAddrMapTranslationEntity,
natAddrMapLocalAddrType,
natAddrMapLocalAddrFrom,
natAddrMapLocalAddrTo,
natAddrMapLocalPortFrom,
natAddrMapLocalPortTo,
natAddrMapGlobalAddrType,
natAddrMapGlobalAddrFrom,
natAddrMapGlobalAddrTo,
natAddrMapGlobalPortFrom,
natAddrMapGlobalPortTo,
natAddrMapProtocol,
natAddrMapStorageType,
natAddrMapRowStatus,
natBindDefIdleTimeout,
natUdpDefIdleTimeout,
natIcmpDefIdleTimeout,
natOtherDefIdleTimeout,
natTcpDefIdleTimeout,
natTcpDefNegTimeout,
natNotifThrottlingInterval }

STATUS deprecated

DESCRIPTION

"A collection of configuration-related information
required to support management of devices supporting
NAT."

::= { natMIBGroups 1 }

natTranslationGroup OBJECT-GROUP

OBJECTS { natAddrBindNumberOfEntries,


```
natAddrBindGlobalAddrType,  
natAddrBindGlobalAddr,  
natAddrBindId,  
natAddrBindTranslationEntity,  
natAddrBindType,  
natAddrBindMapIndex,  
natAddrBindSessions,  
natAddrBindMaxIdleTime,  
natAddrBindCurrentIdleTime,  
natAddrBindInTranslates,  
natAddrBindOutTranslates,  
natAddrPortBindNumberOfEntries,  
natAddrPortBindGlobalAddrType,  
natAddrPortBindGlobalAddr,  
natAddrPortBindGlobalPort,  
natAddrPortBindId,  
natAddrPortBindTranslationEntity,  
natAddrPortBindType,  
natAddrPortBindMapIndex,  
natAddrPortBindSessions,  
natAddrPortBindMaxIdleTime,  
natAddrPortBindCurrentIdleTime,  
natAddrPortBindInTranslates,  
natAddrPortBindOutTranslates,  
natSessionPrivateSrcEPBindId,  
natSessionPrivateSrcEPBindMode,  
natSessionPrivateDstEPBindId,  
natSessionPrivateDstEPBindMode,  
natSessionDirection,  
natSessionUpTime,  
natSessionAddrMapIndex,  
natSessionProtocolType,  
natSessionPrivateAddrType,  
natSessionPrivateSrcAddr,  
natSessionPrivateSrcPort,  
natSessionPrivateDstAddr,  
natSessionPrivateDstPort,  
natSessionPublicAddrType,  
natSessionPublicSrcAddr,  
natSessionPublicSrcPort,  
natSessionPublicDstAddr,  
natSessionPublicDstPort,  
natSessionMaxIdleTime,  
natSessionCurrentIdleTime,  
natSessionInTranslates,  
natSessionOutTranslates }
```

STATUS deprecated


```
DESCRIPTION
    "A collection of BIND-related objects required to support
    management of devices supporting NAT."
 ::= { natMIBGroups 2 }

natStatsInterfaceGroup OBJECT-GROUP
    OBJECTS { natInterfaceInTranslates,
              natInterfaceOutTranslates,
              natInterfaceDiscards }
    STATUS deprecated
    DESCRIPTION
        "A collection of NAT statistics associated with the
        interface on which NAT is configured, to aid
        troubleshooting/monitoring of the NAT operation."
 ::= { natMIBGroups 3 }

natStatsProtocolGroup OBJECT-GROUP
    OBJECTS { natProtocolInTranslates,
              natProtocolOutTranslates,
              natProtocolDiscards }
    STATUS deprecated
    DESCRIPTION
        "A collection of protocol specific NAT statistics,
        to aid troubleshooting/monitoring of NAT operation."
 ::= { natMIBGroups 4 }

natStatsAddrMapGroup OBJECT-GROUP
    OBJECTS { natAddrMapInTranslates,
              natAddrMapOutTranslates,
              natAddrMapDiscards,
              natAddrMapAddrUsed }
    STATUS deprecated
    DESCRIPTION
        "A collection of address map specific NAT statistics,
        to aid troubleshooting/monitoring of NAT operation."
 ::= { natMIBGroups 5 }

natMIBNotificationGroup NOTIFICATION-GROUP
    NOTIFICATIONS { natPacketDiscard }
    STATUS deprecated
    DESCRIPTION
        "A collection of notifications generated by
        devices supporting this MIB."
 ::= { natMIBGroups 6 }

--
-- Compliance statements
```


--

natMIBFullCompliance MODULE-COMPLIANCE

STATUS deprecated

DESCRIPTION

"When this MIB is implemented with support for read-create, then such an implementation can claim full compliance. Such devices can then be both monitored and configured with this MIB.

The following index objects cannot be added as OBJECT clauses but nevertheless have the compliance requirements:

"

```
-- OBJECT  natAddrBindLocalAddrType
-- SYNTAX  InetAddressType { ipv4(1), ipv6(2) }
-- DESCRIPTION
--          "An implementation is required to support
--          global IPv4 and/or IPv6 addresses, depending
--          on its support for IPv4 and IPv6."

-- OBJECT  natAddrBindLocalAddr
-- SYNTAX  InetAddress (SIZE(4|16))
-- DESCRIPTION
--          "An implementation is required to support
--          global IPv4 and/or IPv6 addresses, depending
--          on its support for IPv4 and IPv6."

-- OBJECT  natAddrPortBindLocalAddrType
-- SYNTAX  InetAddressType { ipv4(1), ipv6(2) }
-- DESCRIPTION
--          "An implementation is required to support
--          global IPv4 and/or IPv6 addresses, depending
--          on its support for IPv4 and IPv6."

-- OBJECT  natAddrPortBindLocalAddr
-- SYNTAX  InetAddress (SIZE(4|16))
-- DESCRIPTION
--          "An implementation is required to support
--          global IPv4 and/or IPv6 addresses, depending
--          on its support for IPv4 and IPv6."
```

MODULE IF-MIB -- The interfaces MIB, [RFC2863](#)

```
MANDATORY-GROUPS {
    ifCounterDiscontinuityGroup
}
```

MODULE -- this module


```
MANDATORY-GROUPS { natConfigGroup, natTranslationGroup,
                    natStatsInterfaceGroup }

GROUP      natStatsProtocolGroup
DESCRIPTION
    "This group is optional."
GROUP      natStatsAddrMapGroup
DESCRIPTION
    "This group is optional."
GROUP      natMIBNotificationGroup
DESCRIPTION
    "This group is optional."

OBJECT natAddrMapLocalAddrType
SYNTAX  InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION
    "An implementation is required to support global IPv4
    and/or IPv6 addresses, depending on its support
    for IPv4 and IPv6."

OBJECT natAddrMapLocalAddrFrom
SYNTAX  InetAddress (SIZE(4|16))
DESCRIPTION
    "An implementation is required to support global IPv4
    and/or IPv6 addresses, depending on its support
    for IPv4 and IPv6."

OBJECT natAddrMapLocalAddrTo
SYNTAX  InetAddress (SIZE(4|16))
DESCRIPTION
    "An implementation is required to support global IPv4
    and/or IPv6 addresses, depending on its support
    for IPv4 and IPv6."

OBJECT natAddrMapGlobalAddrType
SYNTAX  InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION
    "An implementation is required to support global IPv4
    and/or IPv6 addresses, depending on its support
    for IPv4 and IPv6."

OBJECT natAddrMapGlobalAddrFrom
SYNTAX  InetAddress (SIZE(4|16))
DESCRIPTION
    "An implementation is required to support global IPv4
    and/or IPv6 addresses, depending on its support
    for IPv4 and IPv6."
```


OBJECT natAddrMapGlobalAddrTo
SYNTAX InetAddress (SIZE(4|16))
DESCRIPTION
"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natAddrBindGlobalAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION
"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natAddrBindGlobalAddr
SYNTAX InetAddress (SIZE(4|16))
DESCRIPTION
"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natAddrPortBindGlobalAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION
"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natAddrPortBindGlobalAddr
SYNTAX InetAddress (SIZE(4|16))
DESCRIPTION
"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natSessionPrivateAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION
"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natSessionPrivateSrcAddr
SYNTAX InetAddress (SIZE(4|16))
DESCRIPTION
"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natSessionPrivateDstAddr
SYNTAX InetAddress (SIZE(4|16))
DESCRIPTION
"An implementation is required to support global IPv4
and/or IPv6 addresses, depending on its support
for IPv4 and IPv6."

OBJECT natSessionPublicAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION
"An implementation is required to support global IPv4
and/or IPv6 addresses, depending on its support
for IPv4 and IPv6."

OBJECT natSessionPublicSrcAddr
SYNTAX InetAddress (SIZE(4|16))
DESCRIPTION
"An implementation is required to support global IPv4
and/or IPv6 addresses, depending on its support
for IPv4 and IPv6."

OBJECT natSessionPublicDstAddr
SYNTAX InetAddress (SIZE(4|16))
DESCRIPTION
"An implementation is required to support global IPv4
and/or IPv6 addresses, depending on its support
for IPv4 and IPv6."

::= { natMIBCompliances 1 }

natMIBReadOnlyCompliance MODULE-COMPLIANCE

STATUS deprecated

DESCRIPTION

"When this MIB is implemented without support for
read-create (i.e., in read-only mode), then such an
implementation can claim read-only compliance.
Such a device can then be monitored but cannot be
configured with this MIB.

The following index objects cannot be added as OBJECT
clauses but nevertheless have the compliance
requirements:

"

-- OBJECT natAddrBindLocalAddrType
-- SYNTAX InetAddressType { ipv4(1), ipv6(2) }
-- DESCRIPTION
-- "An implementation is required to support
-- global IPv4 and/or IPv6 addresses, depending


```
--          on its support for IPv4 and IPv6."

-- OBJECT  natAddrBindLocalAddr
-- SYNTAX  InetAddress (SIZE(4|16))

-- DESCRIPTION
--          "An implementation is required to support
--          global IPv4 and/or IPv6 addresses, depending
--          on its support for IPv4 and IPv6."

-- OBJECT  natAddrPortBindLocalAddrType
-- SYNTAX  InetAddressType { ipv4(1), ipv6(2) }
-- DESCRIPTION
--          "An implementation is required to support
--          global IPv4 and/or IPv6 addresses, depending
--          on its support for IPv4 and IPv6."
-- OBJECT  natAddrPortBindLocalAddr
-- SYNTAX  InetAddress (SIZE(4|16))
-- DESCRIPTION
--          "An implementation is required to support
--          global IPv4 and/or IPv6 addresses, depending
--          on its support for IPv4 and IPv6."
```

MODULE IF-MIB -- The interfaces MIB, [RFC2863](#)

```
MANDATORY-GROUPS {
    ifCounterDiscontinuityGroup
}
```

MODULE -- this module

```
MANDATORY-GROUPS { natConfigGroup, natTranslationGroup,
    natStatsInterfaceGroup }
```

```
GROUP          natStatsProtocolGroup
```

```
DESCRIPTION
```

```
    "This group is optional."
```

```
GROUP          natStatsAddrMapGroup
```

```
DESCRIPTION
```

```
    "This group is optional."
```

```
GROUP          natMIBNotificationGroup
```

```
DESCRIPTION
```

```
    "This group is optional."
```

```
OBJECT natInterfaceRowStatus
```

```
SYNTAX RowStatus { active(1) }
```

```
MIN-ACCESS    read-only
```

```
DESCRIPTION
```

```
    "Write access is not required, and active is the only
    status that needs to be supported."
```


OBJECT natAddrMapLocalAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
MIN-ACCESS read-only
DESCRIPTION
"Write access is not required. An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natAddrMapLocalAddrFrom
SYNTAX InetAddress (SIZE(4|16))
MIN-ACCESS read-only
DESCRIPTION
"Write access is not required. An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natAddrMapLocalAddrTo
SYNTAX InetAddress (SIZE(4|16))
MIN-ACCESS read-only
DESCRIPTION
"Write access is not required. An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natAddrMapGlobalAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
MIN-ACCESS read-only
DESCRIPTION
"Write access is not required. An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natAddrMapGlobalAddrFrom
SYNTAX InetAddress (SIZE(4|16))
MIN-ACCESS read-only
DESCRIPTION
"Write access is not required. An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natAddrMapGlobalAddrTo
SYNTAX InetAddress (SIZE(4|16))
MIN-ACCESS read-only
DESCRIPTION
"Write access is not required. An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natAddrMapRowStatus
SYNTAX RowStatus { active(1) }
MIN-ACCESS read-only
DESCRIPTION
 "Write access is not required, and active is the only
 status that needs to be supported."

OBJECT natAddrBindGlobalAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION
 "An implementation is required to support global IPv4
 and/or IPv6 addresses, depending on its support for
 IPv4 and IPv6."

OBJECT natAddrBindGlobalAddr
SYNTAX InetAddress (SIZE(4|16))
DESCRIPTION
 "An implementation is required to support global IPv4
 and/or IPv6 addresses, depending on its support for
 IPv4 and IPv6."

OBJECT natAddrPortBindGlobalAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION
 "An implementation is required to support global IPv4
 and/or IPv6 addresses, depending on its support for
 IPv4 and IPv6."

OBJECT natAddrPortBindGlobalAddr
SYNTAX InetAddress (SIZE(4|16))
DESCRIPTION
 "An implementation is required to support global IPv4
 and/or IPv6 addresses, depending on its support for
 IPv4 and IPv6."

OBJECT natSessionPrivateAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION
 "An implementation is required to support global IPv4
 and/or IPv6 addresses, depending on its support for
 IPv4 and IPv6."

OBJECT natSessionPrivateSrcAddr
SYNTAX InetAddress (SIZE(4|16))
DESCRIPTION
 "An implementation is required to support global IPv4
 and/or IPv6 addresses, depending on its support for
 IPv4 and IPv6."


```
OBJECT  natSessionPrivateDstAddr
SYNTAX  InetAddress (SIZE(4|16))
DESCRIPTION
    "An implementation is required to support global IPv4
    and/or IPv6 addresses, depending on its support for
    IPv4 and IPv6."

OBJECT  natSessionPublicAddrType
SYNTAX  InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION
    "An implementation is required to support global IPv4
    and/or IPv6 addresses, depending on its support for
    IPv4 and IPv6."

OBJECT  natSessionPublicSrcAddr
SYNTAX  InetAddress (SIZE(4|16))
DESCRIPTION
    "An implementation is required to support global IPv4
    and/or IPv6 addresses, depending on its support for
    IPv4 and IPv6."

OBJECT  natSessionPublicDstAddr
SYNTAX  InetAddress (SIZE(4|16))
DESCRIPTION
    "An implementation is required to support global IPv4
    and/or IPv6 addresses, depending on its support for
    IPv4 and IPv6."
```

```
::= { natMIBCompliances 2 }
```

END

5. Security Considerations

All objects in this MIB module have been deprecated. As a result, security considerations in [[I-D.ietf-behave-nat-mib-v2](#)] apply instead. Amongst other matters, these considerations cover the case where both this MIB module and NAT-MIB-V2 are present. In fact, such a situation is unlikely because [[RFC4008](#)], as a MIB module oriented toward configuration, was overtaken by events and saw little implementation.

6. IANA Considerations

IANA has assigned object identifier 123 to the natMIB module, with prefix iso.org.dod.internet.mgmt.mib-2 in the Network Management Parameters registry [[SMI-NUMBERS](#)].

IANA is requested to mark that identifier as OBSOLETE and to update the reference from [[RFC4008](#)] to the present document.

7. References

7.1. Normative References

- [I-D.ietf-behave-nat-mib-v2]
Perrault, S., Tsou, T., Sivakumar, S., and T. Taylor,
"Definitions of Managed Objects for Network Address
Translators (NAT), Version 2", June 2015.
- [RFC2119] Bradner, S., "Key words for use in RFCs to Indicate
Requirement Levels", [BCP 14](#), [RFC 2119](#), March 1997.
- [RFC2578] McCloghrie, K., Ed., Perkins, D., Ed., and J.
Schoenwaelder, Ed., "Structure of Management Information
Version 2 (SMIv2)", STD 58, [RFC 2578](#), April 1999.
- [RFC2579] McCloghrie, K., Ed., Perkins, D., Ed., and J.
Schoenwaelder, Ed., "Textual Conventions for SMIv2", STD
58, [RFC 2579](#), April 1999.
- [RFC2580] McCloghrie, K., Perkins, D., and J. Schoenwaelder,
"Conformance Statements for SMIv2", STD 58, [RFC 2580](#),
April 1999.
- [RFC3411] Harrington, D., Presuhn, R., and B. Wijnen, "An
Architecture for Describing Simple Network Management
Protocol (SNMP) Management Frameworks", STD 62, [RFC 3411](#),
December 2002.
- [RFC3414] Blumenthal, U. and B. Wijnen, "User-based Security Model
(USM) for version 3 of the Simple Network Management
Protocol (SNMPv3)", STD 62, [RFC 3414](#), December 2002.
- [RFC3826] Blumenthal, U., Maino, F., and K. McCloghrie, "The
Advanced Encryption Standard (AES) Cipher Algorithm in the
SNMP User-based Security Model", [RFC 3826](#), June 2004.
- [RFC4001] Daniele, M., Haberman, B., Routhier, S., and J.
Schoenwaelder, "Textual Conventions for Internet Network
Addresses", [RFC 4001](#), February 2005.
- [RFC5591] Harrington, D. and W. Hardaker, "Transport Security Model
for the Simple Network Management Protocol (SNMP)", STD
78, [RFC 5591](#), June 2009.

- [RFC5592] Harrington, D., Salowey, J., and W. Hardaker, "Secure Shell Transport Model for the Simple Network Management Protocol (SNMP)", [RFC 5592](#), June 2009.
- [RFC6353] Hardaker, W., "Transport Layer Security (TLS) Transport Model for the Simple Network Management Protocol (SNMP)", STD 78, [RFC 6353](#), July 2011.

[7.2.](#) Informative References

- [RFC2663] Srisuresh, P. and M. Holdrege, "IP Network Address Translator (NAT) Terminology and Considerations", [RFC 2663](#), August 1999.
- [RFC3022] Srisuresh, P. and K. Egevang, "Traditional IP Network Address Translator (Traditional NAT)", [RFC 3022](#), January 2001.
- [RFC3410] Case, J., Mundy, R., Partain, D., and B. Stewart, "Introduction and Applicability Statements for Internet-Standard Management Framework", [RFC 3410](#), December 2002.
- [RFC4008] Rohit, R., Srisuresh, P., Raghunarayan, R., Pai, N., and C. Wang, "Definitions of Managed Objects for Network Address Translators (NAT)", [RFC 4008](#), March 2005.
- [SMI-NUMBERS]
"Network Management Parameters registry at IANA",
<<http://www.iana.org/assignments/smi-numbers>>.

Authors' Addresses

Simon Perreault
Jive Communications
Quebec, QC
Canada

Email: sperreault@jive.com

Tina Tsou
Huawei Technologies
Bantian, Longgang District
Shenzhen 518129
PR China

Email: tina.tsou.zouting@huawei.com

Senthil Sivakumar
Cisco Systems
7100-8 Kit Creek Road
Research Triangle Park, North Carolina 27709
USA

Phone: +1 919 392 5158
Email: ssenthil@cisco.com

Tom Taylor
PT Taylor Consulting
Ottawa
Canada

Email: tom.taylor.stds@gmail.com

